



LMT IoT Shortcut SDK API

1.0.3

| | |
|--|----------|
| 1 File Index | 1 |
| 1.1 File List | 1 |
| 2 File Documentation | 2 |
| 2.1 lmt_coap_manager.h File Reference | 2 |
| 2.1.1 Macro Definition Documentation | 3 |
| 2.1.1.1 APP_COAP_MAX_MSG_LEN | 3 |
| 2.1.2 Enumeration Type Documentation | 3 |
| 2.1.2.1 MailerWaitModes | 3 |
| 2.1.3 Function Documentation | 3 |
| 2.1.3.1 getDeviceSN() | 3 |
| 2.1.3.2 getMailerWaitMode() | 4 |
| 2.1.3.3 getNetworkQuality() | 4 |
| 2.1.3.4 getPacketCounter() | 4 |
| 2.1.3.5 getPacketCounterLimit() | 4 |
| 2.1.3.6 isModemInitialized() | 5 |
| 2.1.3.7 isSocketConnected() | 5 |
| 2.1.3.8 modemShutdown() | 5 |
| 2.1.3.9 resetPacketCounter() | 5 |
| 2.1.3.10 sendEventCmdRes() | 5 |
| 2.1.3.11 setMailerWaitMode() | 5 |
| 2.1.3.12 setPacketCounter() | 6 |
| 2.1.3.13 setPacketCounterLimit() | 6 |
| 2.1.3.14 triggerDataPacking() | 6 |
| 2.1.3.15 triggerMailer() | 6 |
| 2.2 lmt_common.h File Reference | 7 |
| 2.2.1 Macro Definition Documentation | 7 |
| 2.2.1.1 FIRST_USER_STATUS_BIT | 7 |
| 2.2.1.2 LAST_USER_STATUS_BIT | 7 |
| 2.2.2 Function Documentation | 7 |
| 2.2.2.1 checkBootOkMask() | 7 |
| 2.2.2.2 criticalError() | 8 |
| 2.2.2.3 resetStatusBit() | 8 |
| 2.2.2.4 setBootOkBit() | 8 |
| 2.2.2.5 setUserBootOkMask() | 8 |
| 2.3 lmt_proto_handler.h File Reference | 9 |
| 2.3.1 Macro Definition Documentation | 10 |
| 2.3.1.1 I_TAPE | 10 |
| 2.3.1.2 MAX_ACTION_PARAMETERS_SIZE | 10 |
| 2.3.1.3 MAX_COLUMNS_COUNT | 10 |
| 2.3.1.4 MAX_PERIODS_COUNT | 10 |
| 2.3.1.5 MAX_TAPE_COUNT | 10 |

| | |
|--|----|
| 2.3.1.6 MAX_TRACKS_COUNT | 10 |
| 2.3.2 Function Documentation | 10 |
| 2.3.2.1 addColumnToTape() | 10 |
| 2.3.2.2 decodeMessage() | 10 |
| 2.3.2.3 dumpMemory() | 11 |
| 2.3.2.4 encodeMessage() | 11 |
| 2.3.2.5 getEncodedMsgBuffer() | 11 |
| 2.3.2.6 getEncodedMsgLen() | 12 |
| 2.3.2.7 getLastPeriod() | 12 |
| 2.3.2.8 getTapeRecordsCount() | 12 |
| 2.3.2.9 isCompressionCheckRequired() | 12 |
| 2.3.2.10 isDataChanged() | 13 |
| 2.3.2.11 isUdpPacketFull() | 13 |
| 2.3.2.12 restartMeasurements() | 13 |
| 2.3.2.13 rewindTape() | 13 |
| 2.3.2.14 updatePeriod() | 13 |
| 2.4 lmt_sdk_api.h File Reference | 14 |
| 2.4.1 Function Documentation | 14 |
| 2.4.1.1 lmtInit() | 14 |
| 2.4.1.2 loop() | 14 |
| 2.4.1.3 setup() | 14 |
| 2.5 lmt_settings.h File Reference | 14 |
| 2.5.1 Enumeration Type Documentation | 16 |
| 2.5.1.1 ActiveSim | 16 |
| 2.5.1.2 LogLevel | 17 |
| 2.5.2 Function Documentation | 17 |
| 2.5.2.1 disableSerialLog() | 17 |
| 2.5.2.2 enableSerialLog() | 17 |
| 2.5.2.3 getActiveSim() | 17 |
| 2.5.2.4 getCoapDeviceName() | 18 |
| 2.5.2.5 getCoapServerHostname() | 18 |
| 2.5.2.6 getCoapServerPort() | 18 |
| 2.5.2.7 getCoapTxFileResource() | 19 |
| 2.5.2.8 getCoapTxFwResource() | 19 |
| 2.5.2.9 getCoapTxResource() | 19 |
| 2.5.2.10 getFileUIRetries() | 19 |
| 2.5.2.11 getLogFileMaxSize() | 20 |
| 2.5.2.12 getLogLevel() | 20 |
| 2.5.2.13 getLogRotationFrequency() | 20 |
| 2.5.2.14 getLTEConnectionTimeout() | 20 |
| 2.5.2.15 getMaxResendAttempts() | 21 |
| 2.5.2.16 getMaxResendTimeout() | 21 |

| | |
|--|----|
| 2.5.2.17 getNoPsmUplinkTimeout() | 21 |
| 2.5.2.18 getNumOfLogFile() | 21 |
| 2.5.2.19 resendPacketInitialTimeout() | 22 |
| 2.5.2.20 getResponseWaitTimeout() | 22 |
| 2.5.2.21 uplinkTimeout() | 22 |
| 2.5.2.22 printCoap() | 22 |
| 2.5.2.23 scanForCoapKeys() | 22 |
| 2.5.2.24 setActiveSim() | 23 |
| 2.5.2.25 setCoapServerHostname() | 23 |
| 2.5.2.26 setCoapServerPort() | 23 |
| 2.5.2.27 setCoapTxFileResource() | 23 |
| 2.5.2.28 setCoapTxFwResource() | 24 |
| 2.5.2.29 setCoapTxResource() | 24 |
| 2.5.2.30 setFileUIRetries() | 24 |
| 2.5.2.31 setLogFileMaxSize() | 24 |
| 2.5.2.32 setLogLevel() | 25 |
| 2.5.2.33 setLogRotationFrequency() | 25 |
| 2.5.2.34 setLTEConnectionTimeout() | 25 |
| 2.5.2.35 setMaxResendAttempts() | 26 |
| 2.5.2.36 setMaxResendTimeout() | 26 |
| 2.5.2.37 setNoPsmUplinkTimeout() | 26 |
| 2.5.2.38 setNumOfLogFile() | 27 |
| 2.5.2.39 resendPacketInitialTimeout() | 27 |
| 2.5.2.40 getResponseWaitTimeout() | 27 |
| 2.5.2.41 uplinkTimeout() | 28 |
| 2.6 lmt_som_event_emitter.h File Reference | 28 |
| 2.6.1 Typedef Documentation | 29 |
| 2.6.1.1 EventHandler | 29 |
| 2.6.2 Enumeration Type Documentation | 29 |
| 2.6.2.1 SomEvent | 29 |
| 2.6.3 Function Documentation | 30 |
| 2.6.3.1 handleSomEvent() | 30 |
| 2.7 lmt_storage_manager.h File Reference | 31 |
| 2.7.1 Function Documentation | 31 |
| 2.7.1.1 checkFwUpgradeStatus() | 31 |
| 2.7.1.2 eraseFlash() | 31 |
| 2.7.1.3 logError() | 31 |
| 2.7.1.4 logInfo() | 32 |
| 2.7.1.5 logInfoFormatted() | 32 |
| 2.7.1.6 logStringHex() | 32 |
| 2.7.1.7 logWarning() | 33 |
| 2.7.1.8 saveSettings() | 33 |

2.7.1.9 settingsFileRead() 33

Index 34

Chapter 1

File Index

1.1 File List

Here is a list of all files with brief descriptions:

| | |
|-----------------------------------|----|
| lmt_coap_manager.h | 2 |
| lmt_common.h | 7 |
| lmt_proto_handler.h | 9 |
| lmt_sdk_api.h | 14 |
| lmt_settings.h | 14 |
| lmt_som_event_emitter.h | 28 |
| lmt_storage_manager.h | 31 |

Chapter 2

File Documentation

2.1 lmt_coap_manager.h File Reference

Macros

- `#define APP_COAP_MAX_MSG_LEN 1280`

Enumerations

- `enum MailerWaitModes { WAIT_ON_TIMEOUT = 0 , WAIT_FOREVER = 1 }`
Enum for mailer wait control.

Functions

- `void getDeviceSN (char *sn_buffer, size_t *buffer_size)`
Reads device serial number (SN).
- `bool isSocketConnected (void)`
Checks if the device is currently connected to the IoT network.
- `bool isModemInitialized (void)`
Checks if the modem is initialized.
- `MailerWaitModes getMailerWaitMode (void)`
Returns the mailer wait mode.
- `void setMailerWaitMode (MailerWaitModes mode)`
Sets the mailer wait mode.
- `uint32_t getPacketCounter (void)`
Retrieves the current packet counter value.
- `void setPacketCounter (uint32_t counter)`
Sets the packet counter to a specific value.
- `void resetPacketCounter (void)`
Resets the packet counter to zero.
- `uint32_t getPacketCounterLimit (void)`
Retrieves the packet counter limit that will trigger the radio data update.
- `void setPacketCounterLimit (uint32_t limit)`
Sets a new packet counter limit that will trigger the radio data update.
- `int getNetworkQuality (int32_t *rsrp, int32_t *rsrq, int32_t *snr)`

- void triggerDataPacking (bool set_include_radio_parms)

Function gets the cached signal quality from the modem.
- void triggerMailer (bool trigger_radio_pata_packing)

Enable packer thread to create a CoAP message.
- void modemShutdown (void)

Function to close the socket and power off the modem.
- void sendEventCmdRes (int res)

Set and send terminal command result.

2.1.1 Macro Definition Documentation

2.1.1.1 APP_COAP_MAX_MSG_LEN

```
#define APP_COAP_MAX_MSG_LEN 1280
```

2.1.2 Enumeration Type Documentation

2.1.2.1 MailerWaitModes

```
enum MailerWaitModes
```

Enum for mailer wait control.

Enumerator

| | |
|-----------------|--|
| WAIT_ON_TIMEOUT | |
| WAIT_FOREVER | |

```
00033 {
00034     WAIT_ON_TIMEOUT = 0,
00035     WAIT_FOREVER   = 1
00036 } MailerWaitModes;
```

2.1.3 Function Documentation

2.1.3.1 getDeviceSN()

```
void getDeviceSN (
    char * sn_buffer,
    size_t * buffer_size)
```

Reads device serial number (SN).

Parameters

| | |
|--------------------|--|
| <i>sn_buffer</i> | Pointer to store the SN. |
| <i>buffer_size</i> | Pointer to buffer size; updated with actual SN length. |

2.1.3.2 getMailerWaitMode()

```
MailerWaitModes getMailerWaitMode (
    void )
```

Returns the mailer wait mode.

Returns

`WAIT_ON_TIMEOUT` (false) if the mailer waits on timeout, `WAIT_FOREVER` (true) if the mailer has to be started by user

2.1.3.3 getNetworkQuality()

```
int getNetworkQuality (
    int32_t * rsrp,
    int32_t * rsrq,
    int32_t * snr)
```

Function gets the cached signal quality from the modem.

Parameters

| | |
|-------------------|---------------------------------|
| <code>rsrp</code> | Pointer to store the RSRP value |
| <code>rsrq</code> | Pointer to store the RSRQ value |
| <code>snr</code> | Pointer to store the SNR value |

Returns

0 if values values, -EINVAL otherwise

2.1.3.4 getPacketCounter()

```
uint32_t getPacketCounter (
    void )
```

Retrieves the current packet counter value.

Returns

Current packet counter value.

2.1.3.5 getPacketCounterLimit()

```
uint32_t getPacketCounterLimit (
    void )
```

Retrieves the packet counter limit that will trigger the radio data update.

Returns

The maximum allowed packet counter value.

2.1.3.6 isModemInitialized()

```
bool isModemInitialized (
    void )
```

Checks if the modem is initialized.

Returns

true if the modem is initialized, false otherwise.

2.1.3.7 isSocketConnected()

```
bool isSocketConnected (
    void )
```

Checks if the device is currently connected to the IoT network.

Returns

true if the device is connected, false otherwise.

2.1.3.8 modemShutdown()

```
void modemShutdown (
    void )
```

Function to close the socket and power off the modem.

2.1.3.9 resetPacketCounter()

```
void resetPacketCounter (
    void )
```

Resets the packet counter to zero.

2.1.3.10 sendEventCmdRes()

```
void sendEventCmdRes (
    int res)
```

Set and send terminal command result.

Parameters

| | |
|------------|--|
| <i>res</i> | Result of the command, 0 if successful, negative value otherwise |
|------------|--|

2.1.3.11 setMailerWaitMode()

```
void setMailerWaitMode (
    MailerWaitModes mode)
```

Sets the mailer wait mode.

Parameters

| | |
|-------------|---|
| <i>mode</i> | WAIT_ON_TIMEOUT (false) if the mailer has to wait on timeout, WAIT_FOREVER (true) if the user controls the mailer start |
|-------------|---|

2.1.3.12 setPacketCounter()

```
void setPacketCounter (
    uint32_t counter)
```

Sets the packet counter to a specific value.

Parameters

| | |
|----------------|---------------------------------------|
| <i>counter</i> | The new value for the packet counter. |
|----------------|---------------------------------------|

2.1.3.13 setPacketCounterLimit()

```
void setPacketCounterLimit (
    uint32_t limit)
```

Sets a new packet counter limit that will trigger the radio data update.

Parameters

| | |
|--------------|---|
| <i>limit</i> | The new upper limit for the packet counter. |
|--------------|---|

2.1.3.14 triggerDataPacking()

```
void triggerDataPacking (
    bool set_include_radio_parms)
```

Enable packer thread to create a CoAP message.

Parameters

| | |
|--------------------------------|------------------------------------|
| <i>set_include_radio_parms</i> | when set, radio data will be added |
|--------------------------------|------------------------------------|

2.1.3.15 triggerMailer()

```
void triggerMailer (
    bool trigger_radio_pata_packing)
```

Enable mailer thread; first data packet containing radio data can be created.

Parameters

| | |
|---|---|
| <code>trigger_radio_pata_packing</code> | when set, radio data packet will be added |
|---|---|

2.2 lmt_common.h File Reference

Macros

- #define FIRST_USER_STATUS_BIT 16
- #define LAST_USER_STATUS_BIT 31

Functions

- void criticalError (void)
Calls assert and triggers system reset in case of critical error.
- bool checkBootOkMask (uint32_t mask)
Returns the flag if the given mask is set in BootOK status.
- void setUserBootOkMask (uint32_t mask)
Set user app boot ok mask.
- void setBootOkBit (uint32_t bit)
Set appropriate status bit.
- void resetStatusBit (uint32_t bit)
Reset appropriate status bit.

2.2.1 Macro Definition Documentation

2.2.1.1 FIRST_USER_STATUS_BIT

```
#define FIRST_USER_STATUS_BIT 16
```

2.2.1.2 LAST_USER_STATUS_BIT

```
#define LAST_USER_STATUS_BIT 31
```

2.2.2 Function Documentation

2.2.2.1 checkBootOkMask()

```
bool checkBootOkMask (
    uint32_t mask)
```

Returns the flag if the given mask is set in BootOK status.

Parameters

| | |
|-------------|----------------------------------|
| <i>mask</i> | The mask of the interested flags |
|-------------|----------------------------------|

Returns

true if all flags are set, false otherwise

2.2.2.2 criticalError()

```
void criticalError (
    void )
```

Calls assert and triggers system reset in case of critical error.

2.2.2.3 resetStatusBit()

```
void resetStatusBit (
    uint32_t bit)
```

Reset appropriate status bit.

Parameters

| | |
|------------|--|
| <i>bit</i> | The number of bit that has to be reset |
|------------|--|

2.2.2.4 setBootOkBit()

```
void setBootOkBit (
    uint32_t bit)
```

Set appropriate status bit.

Parameters

| | |
|------------|--------------------------------------|
| <i>bit</i> | The number of bit that has to be set |
|------------|--------------------------------------|

2.2.2.5 setUserBootOkMask()

```
void setUserBootOkMask (
    uint32_t mask)
```

Set user app boot ok mask.

Parameters

| | |
|-------------------|----------------------------------|
| <code>mask</code> | The mask of the interested flags |
|-------------------|----------------------------------|

2.3 lmt_proto_handler.h File Reference

Macros

- `#define MAX_TRACKS_COUNT 12`
- `#define MAX_PERIODS_COUNT 3`
- `#define MAX_COLUMNS_COUNT 50`
- `#define MAX_TAPE_COUNT 1`
- `#define MAX_ACTION_PARAMETERS_SIZE 256`
- `#define I_TAPE 0`

Functions

- `void dumpMemory (uint8_t *ptr, uint16_t size)`

Dumps in HEX the memory region at the given address of the given size.
- `bool isDataChanged (void)`

Returns flag signalling that data is updated in comparison to the last encoded message.
- `void updatePeriod (uint8_t i_tape, uint32_t value)`

Function to add a new period to the Periods array of a given Tape. During operation first add the period, then measurement. The duplicate value entries will be not added. The entries without measurements will be overwritten. On overflow it will reset the Periods array. Corrects also the Columns_count if Columns_count >= MAX_COLUMNS_COUNT.
- `uint32_t getLastPeriod (uint8_t i_tape)`

Returns the last defined period of the Tape instance given by pointer.
- `intaddColumnToTape (uint8_t i_tape, uint32_t period, int32_t *p_measurements)`

Adds a measurement column and its period to the given Tape.
- `pb_size_t getTapeRecordsCount (uint8_t i_tape)`

Returns actual column count in Tape.
- `void rewindTape (uint8_t i_tape)`

Resets the Tape keeping the last period entry.
- `void restartMeasurements (void)`

Clear sensor measurements keeping the last measurement periods.
- `bool encodeMessage (void)`

Encodes uplink message.
- `uint16_t getEncodedMsgLen (void)`

Get encoded message length.
- `const uint8_t *getEncodedMsgBuffer (void)`

Get pointer to encoded message buffer.
- `bool isCompressionCheckRequired (void)`

Checks if the data will fit UDP packet with no compression.
- `bool isUdpPacketFull (void)`

Checks if the UDP packet is full.
- `bool decodeMessage (const uint8_t *p_buffer)`

Decodes downlink message.

2.3.1 Macro Definition Documentation

2.3.1.1 I_TAPE

```
#define I_TAPE 0
```

2.3.1.2 MAX_ACTION_PARAMETERS_SIZE

```
#define MAX_ACTION_PARAMETERS_SIZE 256
```

2.3.1.3 MAX_COLUMNS_COUNT

```
#define MAX_COLUMNS_COUNT 50
```

2.3.1.4 MAX_PERIODS_COUNT

```
#define MAX_PERIODS_COUNT 3
```

2.3.1.5 MAX_TAPE_COUNT

```
#define MAX_TAPE_COUNT 1
```

2.3.1.6 MAX_TRACKS_COUNT

```
#define MAX_TRACKS_COUNT 12
```

2.3.2 Function Documentation

2.3.2.1 addColumnToTape()

```
int addColumnToTape (
    uint8_t i_tape,
    uint32_t period,
    int32_t * p_measurements)
```

Adds a measuremens column and it period to the given Tape.

Parameters

| | |
|-----------------------|--|
| <i>i_tape</i> | the Tape index |
| <i>period</i> | the period value |
| <i>p_measurements</i> | pointer to the measurements array in count of MAX_TRACKS_COUNT |

Returns

number of remaining empty columns, -EINVAL if *i_tape* is out of range

2.3.2.2 decodeMessage()

```
bool decodeMessage (
    const uint8_t * p_buffer)
```

Decodes downlink message.

Parameters

| | |
|-----------------|-----------------------------|
| <i>p_buffer</i> | pointer to incoming message |
|-----------------|-----------------------------|

Returns

success flag

2.3.2.3 dumpMemory()

```
void dumpMemory (
    uint8_t * ptr,
    uint16_t size)
```

Dumps in HEX the memory region at the given address of the given size.

Parameters

| | |
|-------------|-----------------------------|
| <i>*ptr</i> | The starting memory address |
| <i>size</i> | The size of the memory dump |

2.3.2.4 encodeMessage()

```
bool encodeMessage (
    void )
```

Encodes uplink message.

Returns

success flag

2.3.2.5 getEncodedMsgBuffer()

```
const uint8_t * getEncodedMsgBuffer (
    void )
```

Get pointer to encoded message buffer.

Returns

Constant pointer to encoded message buffer

2.3.2.6 **getEncodedMsgLen()**

```
uint16_t getEncodedMsgLen (
    void )
```

Get encoded message length.

Returns

Current encoded message length

2.3.2.7 **getLastPeriod()**

```
uint32_t getLastPeriod (
    uint8_t i_tape)
```

Returns the last defined period of the Tape instance given by pointer.

Parameters

| | |
|---------------|----------------|
| <i>i_tape</i> | the Tape index |
|---------------|----------------|

Returns

the last defined period or 0 if period is not set

2.3.2.8 **getTapeRecordsCount()**

```
pb_size_t getTapeRecordsCount (
    uint8_t i_tape)
```

Returns actual column count in Tape.

Parameters

| | |
|---------------|----------------|
| <i>i_tape</i> | the Tape index |
|---------------|----------------|

Returns

Column count in Tape

2.3.2.9 **isCompressionCheckRequired()**

```
bool isCompressionCheckRequired (
    void )
```

Checks if the data will fit UDP packet with no compression.

Returns

true if data will not fit, false otherwise

2.3.2.10 isDataChanged()

```
bool isDataChanged (
    void )
```

Returns flag signalising that data is updated in comparison to the last encoded message.

Returns

A flag signalising that data had been changed

2.3.2.11 isUdpPacketFull()

```
bool isUdpPacketFull (
    void )
```

Checks if the UDP packet is full.

Returns

true if full, false otherwise

2.3.2.12 restartMeasurements()

```
void restartMeasurements (
    void )
```

Clear sensor measurements keeping the last measurement periods.

2.3.2.13 rewindTape()

```
void rewindTape (
    uint8_t i_tape)
```

Resets the Tape keeping the last period entry.

Parameters

| | |
|---------------|----------------|
| <i>i_tape</i> | the Tape index |
|---------------|----------------|

2.3.2.14 updatePeriod()

```
void updatePeriod (
    uint8_t i_tape,
    uint32_t value)
```

Function to add a new period to the Periods array of a given Tape. During operation first add the period, then measurement. The duplicate value entries will be not added. The entries without measurements will be overwritten. On overflow it will reset the Periods array. Corrects also the Columns_count if Columns_count >= MAX_COLUMNS-COUNT.

Parameters

| | |
|---------------|------------------|
| <i>i_tape</i> | the Tape index |
| <i>value</i> | the period value |

2.4 lmt_sdk_api.h File Reference

Functions

- void lmtInit (void)
Initializes the SDK.
- void setup (void)
User application setup code.
- void loop (void)
User application main control loop.

2.4.1 Function Documentation

2.4.1.1 lmtInit()

```
void lmtInit (
    void )
```

Initializes the SDK.

2.4.1.2 loop()

```
void loop (
    void )
```

User application main control loop.

2.4.1.3 setup()

```
void setup (
    void )
```

User application setup code.

2.5 lmt_settings.h File Reference

Enumerations

- enum LogLevel { LOG_ERRORS = 0 , LOG_WARNINGS , LOG_INFORMATIVE }
Log level options for system logging.
- enum ActiveSim { ACTIVATE_ESIM = 0 , ACTIVATE_SIM = 1 }
Enum for active SIM control.

Functions

- void printCoap (void)
Prints coap structure.
- int scanForCoapKeys (const uint8_t *p_coap_data, unsigned int size)
Scans a buffer for COAP key/value pairs stored as C strings (key\0value\0).
- void setCoapServerPort (uint16_t port)
Set the COAP server port number.
- void setCoapTxResource (const char *resource)
Set the COAP transmission resource path.
- void setCoapTxFileResource (const char *resource)
Set the COAP file transmission resource path.
- void setCoapTxFwResource (const char *resource)
Set the COAP firmware transmission resource path.
- void setCoapServerHostname (const char *hostname)
Set the hostname of the main COAPS server.
- uint16_t getCoapServerPort (void)
Get the currently configured COAP server port.
- const char * getCoapTxResource (void)
Get the configured COAP transmission resource path.
- const char * getCoapTxFileResource (void)
Get the configured COAP file transmission resource path.
- const char * getCoapTxFwResource (void)
Get the configured COAP firmware transmission resource path.
- void getCoapDeviceName (char *device_name, unsigned *len)
Get the configured device name used in COAP.
- const char * getCoapServerHostname (void)
Get the configured main COAPS server hostname.
- int setLogFileMaxSize (int32_t size)
Set the maximum size of the log file.
- int setLTEConnectionTimeout (uint16_t timeout)
Set network connection timeout.
- int setUplinkTimeout (uint16_t timeout)
Set the device uplink timeout.
- int setNoPsmUplinkTimeout (uint16_t timeout)
Set the device uplink timeout when PSM not available.
- int setResendPacketInitialTimeout (uint8_t timeout)
Set the initial timeout for resending packets.
- int setMaxResendTimeout (uint8_t timeout)
Set the maximum timeout for resending packets.
- int setMaxResendAttempts (uint8_t attempts)
Set the maximum number of resend attempts.
- int setLogRotationFrequency (uint8_t frequency)
Set the frequency of log rotation checks.
- int setResponseWaitTimeout (uint8_t timeout)
Set the CoAP response wait timeout.
- int setFileUIRetries (uint8_t retries)
Set the number of retries for file uploads.
- int setNumOfLogFile (uint8_t file_count)
Set the maximum number of log files on flash before starting file rotation.
- int setLogLevel (LogLevel level)

- `int setActiveSim (ActiveSim sim_source)`

Set the log level for the application.
- `int32_t getLogFileMaxSize (void)`

Gets the current SIM source.
- `uint16_t getLTEConnectionTimeout (void)`

Get the maximum size of the log file.
- `uint16_t getUplinkTimeout (void)`

Get network connection timeout.
- `uint16_t getNoPsmUplinkTimeout (void)`

Get the device uplink timeout.
- `uint8_t getResendPacketInitialTimeout (void)`

Get the device uplink timeout when no PSM available.
- `uint8_t getMaxResendTimeout (void)`

Get the initial timeout for resending packets.
- `uint8_t getMaxResendAttempts (void)`

Get the maximum number of resend attempts.
- `uint8_t getLogRotationFrequency (void)`

Get the frequency of log rotation checks.
- `uint8_t getResponseWaitTimeout (void)`

Get the CoAP response wait timeout.
- `uint8_t getFileUIRetries (void)`

Get the number of retries for file uploads.
- `uint8_t getNumOfLogFile (void)`

Get the maximum number of log file count in flash.
- `LogLevel getLogLevel (void)`

Get the log level for the application.
- `int getActiveSim (ActiveSim *sim_source)`

Returns the current SIM source.
- `uint8_t disableSerialLog (void)`

Disable serial logging output by suspending the UART device.
- `uint8_t enableSerialLog (void)`

Enable serial logging output by resuming the UART device.

2.5.1 Enumeration Type Documentation

2.5.1.1 ActiveSim

```
enum ActiveSim
```

Enum for active SIM control.

Enumerator

| | |
|---------------|--|
| ACTIVATE_ESIM | |
| ACTIVATE_SIM | |

```
00039 {
00040     ACTIVATE_ESIM = 0,
00041     ACTIVATE_SIM  = 1
00042 } ActiveSim;
```

2.5.1.2 LogLevel

```
enum LogLevel
```

Log level options for system logging.

This enum defines the available log levels for controlling the verbosity of saved system logs.

Enumerator

| | |
|-----------------|--|
| LOG_ERRORS | |
| LOG_WARNINGS | |
| LOG_INFORMATIVE | |

```
00029 {
00030     LOG_ERRORS = 0,
00031     LOG_WARNINGS,
00032     LOG_INFORMATIVE
00033 } LogLevel;
```

2.5.2 Function Documentation

2.5.2.1 disableSerialLog()

```
uint8_t disableSerialLog (
    void )
```

Disable serial logging output by suspending the UART device.

Suspends the UART device using power management to disable serial output for logging and debugging. This can help reduce power consumption when serial output is not needed.

Returns

0 on success, negative error code on failure. Returns -EALREADY if the device is already suspended (not treated as error).

2.5.2.2 enableSerialLog()

```
uint8_t enableSerialLog (
    void )
```

Enable serial logging output by resuming the UART device.

Resumes the UART device using power management to enable serial output for logging and debugging. This allows real-time monitoring of device operation after the UART was previously suspended.

Returns

0 on success, negative error code on failure. Returns -EALREADY if the device is already active (not treated as error).

2.5.2.3 getActiveSim()

```
int getActiveSim (
    ActiveSim * sim_source)
```

Returns the current SIM source.

Parameters

| | |
|-------------------|----------------------------------|
| <i>sim_source</i> | Pointer to the source of the SIM |
|-------------------|----------------------------------|

Returns

0 on success, negative error code on failure.

2.5.2.4 getCoapDeviceName()

```
void getCoapDeviceName (
    char * device_name,
    unsigned * len)
```

Get the configured device name used in COAP.

Parameters

| | |
|--------------------|---|
| <i>device_name</i> | Pointer to a buffer where the device name will be stored. |
| <i>len</i> | Length pointer holds in/out buffer size. |

2.5.2.5 getCoapServerHostname()

```
const char * getCoapServerHostname (
    void )
```

Get the configured main COAPS server hostname.

Returns

Null-terminated string with the server hostname.

2.5.2.6 getCoapServerPort()

```
uint16_t getCoapServerPort (
    void )
```

Get the currently configured COAP server port.

Returns

Server port as uint16_t.

2.5.2.7 getCoapTxFileResource()

```
const char * getCoapTxFileResource (
    void )
```

Get the configured COAP file transmission resource path.

Returns

Null-terminated string representing the file resource path.

2.5.2.8 getCoapTxFwResource()

```
const char * getCoapTxFwResource (
    void )
```

Get the configured COAP firmware transmission resource path.

Returns

Null-terminated string representing the firmware resource path.

2.5.2.9 getCoapTxResource()

```
const char * getCoapTxResource (
    void )
```

Get the configured COAP transmission resource path.

Returns

Null-terminated string representing the resource path.

2.5.2.10 getFileUlRetries()

```
uint8_t getFileUlRetries (
    void )
```

Get the number of retries for file uploads.

Returns

Number of retries for file uploads.

2.5.2.11 `getLogFileMaxSize()`

```
int32_t getLogFileMaxSize (
    void )
```

Get the maximum size of the log file.

Returns

Maximum size of the log file in bytes.

2.5.2.12 `getLogLevel()`

```
LogLevel getLogLevel (
    void )
```

Get the log level for the application.

Returns

Log level for the application.

2.5.2.13 `getLogRotationFrequency()`

```
uint8_t getLogRotationFrequency (
    void )
```

Get the frequency of log rotation checks.

Returns

Frequency of log rotation checks in wakeup cycles.

2.5.2.14 `getLTEConnectionTimeout()`

```
uint16_t getLTEConnectionTimeout (
    void )
```

Get network connection timeout.

Returns

Device network connection timeout in seconds.

2.5.2.15 getMaxResendAttempts()

```
uint8_t getMaxResendAttempts (
    void )
```

Get the maximum number of resend attempts.

Returns

Maximum number of resend attempts before the socket is closed.

2.5.2.16 getMaxResendTimeout()

```
uint8_t getMaxResendTimeout (
    void )
```

Get the maximum timeout for resending packets.

Returns

Maximum timeout for resending packets in hours.

2.5.2.17 getNoPsmUplinkTimeout()

```
uint16_t getNoPsmUplinkTimeout (
    void )
```

Get the device uplink timeout when no PSM available.

Returns

Device uplink timeout when PSM not available in hours.

2.5.2.18 getNumOfLogFile()

```
uint8_t getNumOfLogFile (
    void )
```

Get the maximum number of log file count in flash.

Returns

Number of maximum count of log files stored in flash.

2.5.2.19 `getResendPacketInitialTimeout()`

```
uint8_t getResendPacketInitialTimeout (
    void )
```

Get the initial timeout for resending packets.

Returns

Initial timeout for resending packets in minutes.

2.5.2.20 `getResponseWaitTimeout()`

```
uint8_t getResponseWaitTimeout (
    void )
```

Get the CoAP response wait timeout.

Returns

Timeout for waiting for CoAP response in seconds.

2.5.2.21 `getUplinkTimeout()`

```
uint16_t getUplinkTimeout (
    void )
```

Get the device uplink timeout.

Returns

Device uplink timeout in minutes.

2.5.2.22 `printCoap()`

```
void printCoap (
    void )
```

Prints coap structure.

2.5.2.23 `scanForCoapKeys()`

```
int scanForCoapKeys (
    const uint8_t * p_coap_data,
    unsigned int size)
```

Scans a buffer for COAP key/value pairs stored as C strings (key\0value\0).

Parameters

| | |
|--------------------|---------------|
| <i>p_coap_data</i> | a Pointer |
| <i>size</i> | Size to scan. |

Returns

0 on success, negative error code on failure.

2.5.2.24 setActiveSim()

```
int setActiveSim (
    ActiveSim sim_source)
```

Sets the current SIM source.

Parameters

| | |
|-------------------|-------------------|
| <i>sim_source</i> | Source of the SIM |
|-------------------|-------------------|

Returns

0 on success, negative error code on failure.

2.5.2.25 setCoapServerHostname()

```
void setCoapServerHostname (
    const char * hostname)
```

Set the hostname of the main COAPS server.

Parameters

| | |
|-----------------|--|
| <i>hostname</i> | Null-terminated string with the server's hostname or IP address. |
|-----------------|--|

2.5.2.26 setCoapServerPort()

```
void setCoapServerPort (
    uint16_t port)
```

Set the COAP server port number.

Parameters

| | |
|-------------|---|
| <i>port</i> | COAP server port (typically 5683 for COAP, 5684 for COAPS). |
|-------------|---|

2.5.2.27 setCoapTxFileResource()

```
void setCoapTxFileResource (
    const char * resource)
```

Set the COAP file transmission resource path.

Parameters

| | |
|-----------------|---|
| <i>resource</i> | Null-terminated string for the file resource (e.g. "upload"). |
|-----------------|---|

2.5.2.28 setCoapTxFwResource()

```
void setCoapTxFwResource (
    const char * resource)
```

Set the COAP firmware transmission resource path.

Parameters

| | |
|-----------------|--|
| <i>resource</i> | Null-terminated string for the firmware update resource. |
|-----------------|--|

2.5.2.29 setCoapTxResource()

```
void setCoapTxResource (
    const char * resource)
```

Set the COAP transmission resource path.

Parameters

| | |
|-----------------|---|
| <i>resource</i> | Null-terminated string representing the resource path (e.g. "sensor/data"). |
|-----------------|---|

2.5.2.30 setFileUIRetries()

```
int setFileUIRetries (
    uint8_t retries)
```

Set the number of retries for file uploads.

Parameters

| | |
|----------------|---|
| <i>retries</i> | Number of retries for file uploads. $1 \leq \text{retries} \leq 10$. |
|----------------|---|

Returns

0 on success, -EINVAL otherwise.

2.5.2.31 setLogFileMaxSize()

```
int setLogFileMaxSize (
    int32_t size)
```

Set the maximum size of the log file.

Parameters

| | |
|-------------|--|
| <i>size</i> | Maximum size of the log file in bytes. 1024 (KB) <= size <= 1048576 (1MB). |
|-------------|--|

Returns

0 on success, -EINVAL otherwise.

2.5.2.32 setLogLevel()

```
int setLogLevel (
    LogLevel level)
```

Set the log level for the application.

Parameters

| | |
|--------------|---|
| <i>level</i> | Log level for the application. LOG_ERRORS, LOG_WARNINGS, LOG_INFORMATIVE. |
|--------------|---|

Returns

0 on success, -EINVAL otherwise.

2.5.2.33 setLogRotationFrequency()

```
int setLogRotationFrequency (
    uint8_t frequency)
```

Set the frequency of log rotation checks.

Parameters

| | |
|------------------|--|
| <i>frequency</i> | Frequency of log rotation checks in wakeup cycles. 1 <= frequency <= 50. |
|------------------|--|

Returns

0 on success, -EINVAL otherwise.

2.5.2.34 setLTEConnectionTimeout()

```
int setLTEConnectionTimeout (
    uint16_t timeout)
```

Set network connection timeout.

Parameters

| | |
|----------------|--|
| <i>timeout</i> | Device network connection timeout in seconds. 1 (sec) <= timeout <= 1800 (30 min). |
|----------------|--|

Returns

0 on success, -EINVAL otherwise.

2.5.2.35 setMaxResendAttempts()

```
int setMaxResendAttempts (
    uint8_t attempts)
```

Set the maximum number of resend attempts.

Parameters

| | |
|-----------------|---|
| <i>attempts</i> | Maximum number of resend attempts before the socket is closed. 1 <= attempts <= 10. |
|-----------------|---|

Returns

0 on success, -EINVAL otherwise.

2.5.2.36 setMaxResendTimeout()

```
int setMaxResendTimeout (
    uint8_t timeout)
```

Set the maximum timeout for resending packets.

Parameters

| | |
|----------------|--|
| <i>timeout</i> | Maximum timeout for resending packets in hours. 1 (h) <= timeout <= 24 (1d). |
|----------------|--|

Returns

0 on success, -EINVAL otherwise.

2.5.2.37 setNoPsmUplinkTimeout()

```
int setNoPsmUplinkTimeout (
    uint16_t timeout)
```

Set the device uplink timeout when PSM not available.

Parameters

| | |
|----------------|---|
| <i>timeout</i> | Device uplink timeout in hours $1 \leq \text{timeout} \leq 24$ (hours). |
|----------------|---|

Returns

0 on success, -EINVAL otherwise.

2.5.2.38 setNumOfLogFiles()

```
int setNumOfLogFiles (
    uint8_t file_count)
```

Set the maximum number of log files on flash before starting file rotation.

Parameters

| | |
|-------------------|---|
| <i>file_count</i> | Number of log files on flash. $1 \leq \text{file_count} \leq 20$. |
|-------------------|---|

Returns

0 on success, -EINVAL otherwise.

2.5.2.39 setResendPacketInitialTimeout()

```
int setResendPacketInitialTimeout (
    uint8_t timeout)
```

Set the initial timeout for resending packets.

Parameters

| | |
|----------------|---|
| <i>timeout</i> | Initial timeout for resending packets in minutes. 1 (min) $\leq \text{timeout} \leq 60$ (1h). |
|----------------|---|

Returns

0 on success, -EINVAL otherwise.

2.5.2.40 setResponseWaitTimeout()

```
int setResponseWaitTimeout (
    uint8_t timeout)
```

Set the CoAP response wait timeout.

Parameters

| | |
|----------------|---|
| <i>timeout</i> | Timeout for waiting for CoAP response in seconds. 1 <= timeout <= 60. |
|----------------|---|

Returns

0 on success, -EINVAL otherwise.

2.5.2.41 setUplinkTimeout()

```
int setUplinkTimeout (
    uint16_t timeout)
```

Set the device uplink timeout.

Parameters

| | |
|----------------|---|
| <i>timeout</i> | Device uplink timeout in minutes. 5 (min) <= timeout <= 1440 (24h). |
|----------------|---|

Returns

0 on success, -EINVAL otherwise.

2.6 lmt_som_event_emitter.h File Reference**TypeDefs**

- `typedef void(* EventHandler) (void *p_data, int i_data)`

Enumerations

- `enum SomEvent {`
- `EVENT_DEVICE_INIT_OK,`
- `EVENT_LOGGER_INIT_OK,`
- `EVENT_PACKER_INIT_OK,`
- `EVENT_MAILER_INIT_OK,`
- `EVENT_DROPPING_OLDEST,`
- `EVENT_PACKER_STARTED,`
- `EVENT_PACKING_FAILED, EVENT_ENQUEUE_FAILED,`
- `EVENT_PACKER_DONE_OK,`
- `EVENT_UL_START,`
- `EVENT_UL_MAX_RETRY,`
- `EVENT_UL_RETRY,`
- `EVENT_UL_DONE,`
- `EVENT_RRC_IDLE,`
- `EVENT_RRC_CONNECTED,`
- `EVENT_MODEM_ON,`
- `EVENT_MODEM_OFF,`
- `EVENT_COAP_START,`
- `EVENT_COAP_FAIL, EVENT_COAP_NOACK,`

```

EVENT_COAP_OK,
EVENT_LOG_ERROR,
EVENT_LOG_WARNING,
EVENT_LOG_INFO,
EVENT_TERMINAL_CMD,
EVENT_COUNT
}

```

Events emitted by the IoT Shortcut SDK library.

Functions

- void handleSomEvent (SomEvent event, void *p_data, int i_data)

Centralized event handler for the library. This is a weak function that can be overridden by the user application.

2.6.1 Typedef Documentation

2.6.1.1 EventHandler

```
typedef void(* EventHandler) (void *p_data, int i_data)
```

2.6.2 Enumeration Type Documentation

2.6.2.1 SomEvent

```
enum SomEvent
```

Events emitted by the IoT Shortcut SDK library.

This enumeration defines all possible events that can be emitted by the library to notify the application about various system and application-level occurrences, such as initialization, uplink status, logging, and terminal commands.

Enumerator

| | |
|-----------------------|--|
| EVENT_DEVICE_INIT_OK | Device initialization completed successfully. |
| EVENT_LOGGER_INIT_OK | Logger module initialized successfully. |
| EVENT_PACKER_INIT_OK | Packer module initialized successfully. |
| EVENT_MAILER_INIT_OK | Mailer module initialized successfully. |
| EVENT_DROPPING_OLDEST | Uplink queue is full, the oldest message(s) are dropped. |
| EVENT_PACKER_STARTED | Packer started. |
| EVENT_PACKING_FAILED | Data packing failed. |
| EVENT_ENQUEUE_FAILED | Packer failed to enqueue packet. |
| EVENT_PACKER_DONE_OK | Package created and enqueued successfully. |
| EVENT_UL_START | Uplink process started. |
| EVENT_UL_MAX_RETRY | Uplink retry limit reached. |
| EVENT_UL_RETRY | Uplink retry is being attempted. |
| EVENT_UL_DONE | Uplink completed. |
| EVENT_RRC_IDLE | RRC connection entered idle state. |
| EVENT_RRC_CONNECTED | RRC connection entered connected state. |
| EVENT_MODEM_ON | Modem is actively consuming power. |

Enumerator

| | |
|--------------------|--|
| EVENT_MODEM_OFF | Modem is powered off to save energy. |
| EVENT_COAP_START | COAP packet uplink started. |
| EVENT_COAP_FAIL | COAP packet uplink failed. |
| EVENT_COAP_NOACK | No ACK received for the COAP packet. |
| EVENT_COAP_OK | COAP packet uplink completed successfully. |
| EVENT_LOG_ERROR | An error log event occurred. |
| EVENT_LOG_WARNING | A warning log event occurred. |
| EVENT_LOG_INFO | An informational log event occurred. |
| EVENT_TERMINAL_CMD | A terminal command event occurred. |
| EVENT_COUNT | Event count. |

```

00030 {
00031     EVENT_DEVICE_INIT_OK,
00032     EVENT_LOGGER_INIT_OK,
00033     EVENT_PACKER_INIT_OK,
00034     EVENT_MAILER_INIT_OK,
00035
00036     EVENT_DROPPING_OLDEST,
00037
00038     EVENT_PACKER_STARTED,
00039     EVENT_PACKING_FAILED,
00040     EVENT_ENQUEUE_FAILED,
00041     EVENT_PACKER_DONE_OK,
00042
00043     EVENT_UL_START,
00044     EVENT_UL_MAX_RETRY,
00045     EVENT_UL_RETRY,
00046     EVENT_UL_DONE,
00047
00048     EVENT_RRC_IDLE,
00049     EVENT_RRC_CONNECTED,
00050
00051     EVENT_MODEM_ON,
00052     EVENT_MODEM_OFF,
00053
00054     EVENT_COAP_START,
00055     EVENT_COAP_FAIL,
00056     EVENT_COAP_NOACK,
00057     EVENT_COAP_OK,
00058
00059     EVENT_LOG_ERROR,
00060     EVENT_LOG_WARNING,
00061     EVENT_LOG_INFO,
00062     EVENT_TERMINAL_CMD,
00063     EVENT_COUNT
00064 } SomEvent;

```

2.6.3 Function Documentation

2.6.3.1 handleSomEvent()

```

void handleSomEvent (
    SomEvent event,
    void * p_data,
    int i_data)

```

Centralized event handler for the library. This is a weak function that can be overridden by the user application.

Parameters

| | |
|---------------|---|
| <i>event</i> | The event type. |
| <i>p_data</i> | Optional data pointer associated with the event (can be NULL). |
| <i>i_data</i> | Optional integer data associated with the event if specified in the event description (e.g., length of the data). |

2.7 lmt_storage_manager.h File Reference

Functions

- int logError (char *text, int code)

Writes error to app.log file.
- int logWarning (char *text)

Writes warning to app.log file.
- void logStringHex (uint8_t *payload, uint8_t message_length)

Logs the given buffer as hex string.
- int logInfoFormatted (char *text,...)

Variadic function for writing formatted info to app.log file.
- int logInfo (char *text)

Function for writing informative string to app.log file. Creating two separate functions because most of the time we don't need to format the string.
- int saveSettings (void)

Writes current device settings in JSON format to settings.txt file.
- void settingsFileRead (void)

Schedules settings.txt read.
- int checkFwUpgradeStatus (void)

Checks if firmware upgrade was successful or failed. Detects successful upgrades by checking if running unconfirmed image. Detects failed upgrades by checking for rejected images in secondary slot.
- int eraseFlash (void)

Wrapper function for filesystem flashErase()

2.7.1 Function Documentation

2.7.1.1 checkFwUpgradeStatus()

```
int checkFwUpgradeStatus (
    void )
```

Checks if firmware upgrade was successful or failed. Detects successful upgrades by checking if running unconfirmed image. Detects failed upgrades by checking for rejected images in secondary slot.

Returns

1 if firmware upgrade was successful, 0 if no upgrade occurred, -1 if upgrade failed

2.7.1.2 eraseFlash()

```
int eraseFlash (
    void )
```

Wrapper function for filesystem flashErase()

Returns

0 on success, negative error code on fail

2.7.1.3 logError()

```
int logError (
    char * text,
    int code)
```

Writes error to app.log file.

Parameters

| | |
|-------------|---------------|
| <i>text</i> | Error string. |
| <i>code</i> | Error code. |

Returns

0 on success, negative value on fail

2.7.1.4 logInfo()

```
int logInfo (
    char * text)
```

Function for writing informative string to app.log file. Creating two separate functions because most of the time we don't need to format the string.

Parameters

| | |
|-------------|----------------------|
| <i>text</i> | info message string. |
|-------------|----------------------|

Returns

0 on success, negative value on fail

2.7.1.5 logInfoFormatted()

```
int logInfoFormatted (
    char * text,
    ...)
```

Variadic function for writing formatted info to app.log file.

Parameters

| | |
|-------------|----------------------|
| <i>text</i> | info message string. |
|-------------|----------------------|

Returns

0 on success, negative value on fail

2.7.1.6 logStringHex()

```
void logStringHex (
    uint8_t * payload,
    uint8_t message_length)
```

Logs the given buffer as hex string.

Parameters

| | |
|-----------------------|-----------------------|
| <i>payload</i> | pointer to the buffer |
| <i>message_length</i> | buffer size |

2.7.1.7 logWarning()

```
int logWarning (
    char * text)
```

Writes warning to app.log file.

Parameters

| | |
|-------------|-----------------|
| <i>text</i> | Warning string. |
|-------------|-----------------|

Returns

0 on success, negative value on fail

2.7.1.8 saveSettings()

```
int saveSettings (
    void )
```

Writes current device settings in JSON format to settings.txt file.

Returns

0 on success, negative value on fail

2.7.1.9 settingsFileRead()

```
void settingsFileRead (
    void )
```

Schedules settings.txt read.

Index

ACTIVATE_ESIM
 lmt_settings.h, 16

ACTIVATE_SIM
 lmt_settings.h, 16

ActiveSim
 lmt_settings.h, 16

addColumnToTape
 lmt_proto_handler.h, 10

APP_COAP_MAX_MSG_LEN
 lmt_coap_manager.h, 3

checkBootOkMask
 lmt_common.h, 7

checkFwUpgradeStatus
 lmt_storage_manager.h, 31

criticalError
 lmt_common.h, 8

decodeMessage
 lmt_proto_handler.h, 10

disableSerialLog
 lmt_settings.h, 17

dumpMemory
 lmt_proto_handler.h, 11

enableSerialLog
 lmt_settings.h, 17

encodeMessage
 lmt_proto_handler.h, 11

eraseFlash
 lmt_storage_manager.h, 31

EVENT_COAP_FAIL
 lmt_som_event_emitter.h, 30

EVENT_COAP_NOACK
 lmt_som_event_emitter.h, 30

EVENT_COAP_OK
 lmt_som_event_emitter.h, 30

EVENT_COAP_START
 lmt_som_event_emitter.h, 30

EVENT_COUNT
 lmt_som_event_emitter.h, 30

EVENT_DEVICE_INIT_OK
 lmt_som_event_emitter.h, 29

EVENT_DROPPING_OLDEST
 lmt_som_event_emitter.h, 29

EVENT_ENQUEUE_FAILED
 lmt_som_event_emitter.h, 29

EVENT_LOG_ERROR
 lmt_som_event_emitter.h, 30

EVENT_LOG_INFO
 lmt_som_event_emitter.h, 30

 lmt_som_event_emitter.h, 30

EVENT_LOG_WARNING
 lmt_som_event_emitter.h, 30

EVENT_LOGGER_INIT_OK
 lmt_som_event_emitter.h, 29

EVENT_MAILER_INIT_OK
 lmt_som_event_emitter.h, 29

EVENT_MODEM_OFF
 lmt_som_event_emitter.h, 30

EVENT_MODEM_ON
 lmt_som_event_emitter.h, 29

EVENT_PACKER_DONE_OK
 lmt_som_event_emitter.h, 29

EVENT_PACKER_INIT_OK
 lmt_som_event_emitter.h, 29

EVENT_PACKER_STARTED
 lmt_som_event_emitter.h, 29

EVENT_PACKING_FAILED
 lmt_som_event_emitter.h, 29

EVENT_RRC_CONNECTED
 lmt_som_event_emitter.h, 29

EVENT_RRC_IDLE
 lmt_som_event_emitter.h, 29

EVENT_TERMINAL_CMD
 lmt_som_event_emitter.h, 30

EVENT_UL_DONE
 lmt_som_event_emitter.h, 29

EVENT_UL_MAX_RETRY
 lmt_som_event_emitter.h, 29

EVENT_UL_RETRY
 lmt_som_event_emitter.h, 29

EVENT_UL_START
 lmt_som_event_emitter.h, 29

EventHandler
 lmt_som_event_emitter.h, 29

FIRST_USER_STATUS_BIT
 lmt_common.h, 7

getActiveSim
 lmt_settings.h, 17

getCoapDeviceName
 lmt_settings.h, 18

getCoapServerHostname
 lmt_settings.h, 18

getCoapServerPort
 lmt_settings.h, 18

getCoapTxFileResource
 lmt_settings.h, 18

getCoapTxFwResource

lmt_settings.h, 19
getCoapTxResource
 lmt_settings.h, 19
getDeviceSN
 lmt_coap_manager.h, 3
getEncodedMsgBuffer
 lmt_proto_handler.h, 11
getEncodedMsgLen
 lmt_proto_handler.h, 11
getFileUIRetries
 lmt_settings.h, 19
getLastPeriod
 lmt_proto_handler.h, 12
getLogFileMaxSize
 lmt_settings.h, 19
getLogLevel
 lmt_settings.h, 20
getLogRotationFrequency
 lmt_settings.h, 20
getLTEConnectionTimeout
 lmt_settings.h, 20
getMailerWaitMode
 lmt_coap_manager.h, 3
getMaxResendAttempts
 lmt_settings.h, 20
getMaxResendTimeout
 lmt_settings.h, 21
getNetworkQuality
 lmt_coap_manager.h, 4
getNoPsmUplinkTimeout
 lmt_settings.h, 21
getNumOfLogFile
 lmt_settings.h, 21
getPacketCounter
 lmt_coap_manager.h, 4
getPacketCounterLimit
 lmt_coap_manager.h, 4
getResendPacketInitialTimeout
 lmt_settings.h, 21
getResponseWaitTimeout
 lmt_settings.h, 22
getTapeRecordsCount
 lmt_proto_handler.h, 12
getUplinkTimeout
 lmt_settings.h, 22

handleSomEvent
 lmt_som_event_emitter.h, 30

I_TAPE
 lmt_proto_handler.h, 10
isCompressionCheckRequired
 lmt_proto_handler.h, 12
isDataChanged
 lmt_proto_handler.h, 12
isModemInitialized
 lmt_coap_manager.h, 4
isSocketConnected
 lmt_coap_manager.h, 5

 isUdpPacketFull
 lmt_proto_handler.h, 13
 LAST_USER_STATUS_BIT
 lmt_common.h, 7
 lmt_coap_manager.h, 2
 APP_COAP_MAX_MSG_LEN, 3
 getDeviceSN, 3
 getMailerWaitMode, 3
 getNetworkQuality, 4
 getPacketCounter, 4
 getPacketCounterLimit, 4
 isModemInitialized, 4
 isSocketConnected, 5
 MailerWaitModes, 3
 modemShutdown, 5
 resetPacketCounter, 5
 sendEventCmdRes, 5
 setMailerWaitMode, 5
 setPacketCounter, 6
 setPacketCounterLimit, 6
 triggerDataPacking, 6
 triggerMailer, 6
 WAIT_FOREVER, 3
 WAIT_ON_TIMEOUT, 3

lmt_common.h, 7
 checkBootOkMask, 7
 criticalError, 8
 FIRST_USER_STATUS_BIT, 7
 LAST_USER_STATUS_BIT, 7
 resetStatusBit, 8
 setBootOkBit, 8
 setUserBootOkMask, 8

lmt_proto_handler.h, 9
 addColumnToTape, 10
 decodeMessage, 10
 dumpMemory, 11
 encodeMessage, 11
 getEncodedMsgBuffer, 11
 getEncodedMsgLen, 11
 getLastPeriod, 12
 getTapeRecordsCount, 12
 I_TAPE, 10
 isCompressionCheckRequired, 12
 isDataChanged, 12
 isUdpPacketFull, 13
 MAX_ACTION_PARAMETERS_SIZE, 10
 MAX_COLUMNS_COUNT, 10
 MAX_PERIODS_COUNT, 10
 MAX_TAPE_COUNT, 10
 MAX_TRACKS_COUNT, 10
 restartMeasurements, 13
 rewindTape, 13
 updatePeriod, 13

 lmt_sdk_api.h, 14
 lmtInit, 14
 loop, 14
 setup, 14
 lmt_settings.h, 14

ACTIVATE_ESIM, 16
 ACTIVATE_SIM, 16
 ActiveSim, 16
 disableSerialLog, 17
 enableSerialLog, 17
 getActiveSim, 17
 getCoapDeviceName, 18
 getCoapServerHostname, 18
 getCoapServerPort, 18
 getCoapTxFileResource, 18
 getCoapTxFwResource, 19
 getCoapTxResource, 19
 getFileUIRetries, 19
 getLogFileMaxSize, 19
 getLogLevel, 20
 getLogRotationFrequency, 20
 getLTEConnectionTimeout, 20
 getMaxResendAttempts, 20
 getMaxResendTimeout, 21
 getNoPsmUplinkTimeout, 21
 getNumOfLogFiles, 21
 getResendPacketInitialTimeout, 21
 getResponseWaitTimeout, 22
 getUplinkTimeout, 22
 LOG_ERRORS, 17
 LOG_INFORMATIVE, 17
 LOG_WARNINGS, 17
 LogLevel, 16
 printCoap, 22
 scanForCoapKeys, 22
 setActiveSim, 23
 setCoapServerHostname, 23
 setCoapServerPort, 23
 setCoapTxFileResource, 23
 setCoapTxFwResource, 24
 setCoapTxResource, 24
 setFileUIRetries, 24
 setLogFileMaxSize, 24
 setLogLevel, 25
 setLogRotationFrequency, 25
 setLTEConnectionTimeout, 25
 setMaxResendAttempts, 26
 setMaxResendTimeout, 26
 setNoPsmUplinkTimeout, 26
 setNumOfLogFiles, 27
 setResendPacketInitialTimeout, 27
 setResponseWaitTimeout, 27
 setUplinkTimeout, 28
 lmt_som_event_emitter.h, 28
 EVENT_COAP_FAIL, 30
 EVENT_COAP_NOACK, 30
 EVENT_COAP_OK, 30
 EVENT_COAP_START, 30
 EVENT_COUNT, 30
 EVENT_DEVICE_INIT_OK, 29
 EVENT_DROPPING_OLDEST, 29
 EVENT_ENQUEUE_FAILED, 29
 EVENT_LOG_ERROR, 30
 EVENT_LOG_INFO, 30
 EVENT_LOG_WARNING, 30
 EVENT_LOGGER_INIT_OK, 29
 EVENT_MAILER_INIT_OK, 29
 EVENT_MODEM_OFF, 30
 EVENT_MODEM_ON, 29
 EVENT_PACKER_DONE_OK, 29
 EVENT_PACKER_INIT_OK, 29
 EVENT_PACKER_STARTED, 29
 EVENT_PACKING_FAILED, 29
 EVENT_RRC_CONNECTED, 29
 EVENT_RRC_IDLE, 29
 EVENT_TERMINAL_CMD, 30
 EVENT_UL_DONE, 29
 EVENT_UL_MAX_RETRY, 29
 EVENT_UL_RETRY, 29
 EVENT_UL_START, 29
 EventHandler, 29
 handleSomEvent, 30
 SomEvent, 29
 lmt_storage_manager.h, 31
 checkFwUpgradeStatus, 31
 eraseFlash, 31
 logError, 31
 logInfo, 32
 logInfoFormatted, 32
 logStringHex, 32
 logWarning, 33
 saveSettings, 33
 settingsFileRead, 33
 lmtInit
 lmt_sdk_api.h, 14
 LOG_ERRORS
 lmt_settings.h, 17
 LOG_INFORMATIVE
 lmt_settings.h, 17
 LOG_WARNINGS
 lmt_settings.h, 17
 logError
 lmt_storage_manager.h, 31
 logInfo
 lmt_storage_manager.h, 32
 logInfoFormatted
 lmt_storage_manager.h, 32
 LogLevel
 lmt_settings.h, 16
 logStringHex
 lmt_storage_manager.h, 32
 logWarning
 lmt_storage_manager.h, 33
 loop
 lmt_sdk_api.h, 14
 MailerWaitModes
 lmt_coap_manager.h, 3
 MAX_ACTION_PARAMETERS_SIZE
 lmt_proto_handler.h, 10
 MAX_COLUMNS_COUNT
 lmt_proto_handler.h, 10

MAX_PERIODS_COUNT
 lmt_proto_handler.h, 10
MAX_TAPE_COUNT
 lmt_proto_handler.h, 10
MAX_TRACKS_COUNT
 lmt_proto_handler.h, 10
modemShutdown
 lmt_coap_manager.h, 5

printCoap
 lmt_settings.h, 22

resetPacketCounter
 lmt_coap_manager.h, 5
resetStatusBit
 lmt_common.h, 8
restartMeasurements
 lmt_proto_handler.h, 13
rewindTape
 lmt_proto_handler.h, 13

saveSettings
 lmt_storage_manager.h, 33
scanForCoapKeys
 lmt_settings.h, 22
sendEventCmdRes
 lmt_coap_manager.h, 5
setActiveSim
 lmt_settings.h, 23
setBootOkBit
 lmt_common.h, 8
setCoapServerHostname
 lmt_settings.h, 23
setCoapServerPort
 lmt_settings.h, 23
setCoapTxFileResource
 lmt_settings.h, 23
setCoapTxFwResource
 lmt_settings.h, 24
setCoapTxResource
 lmt_settings.h, 24
setFileUIRetries
 lmt_settings.h, 24
setLogFileMaxSize
 lmt_settings.h, 24
setLogLevel
 lmt_settings.h, 25
setLogRotationFrequency
 lmt_settings.h, 25
setLTEConnectionTimeout
 lmt_settings.h, 25
setMailerWaitMode
 lmt_coap_manager.h, 5
setMaxResendAttempts
 lmt_settings.h, 26
setMaxResendTimeout
 lmt_settings.h, 26
setNoPsmUplinkTimeout
 lmt_settings.h, 26

setNumOfFileLogs
 lmt_settings.h, 27
setPacketCounter
 lmt_coap_manager.h, 6
setPacketCounterLimit
 lmt_coap_manager.h, 6
setResendPacketInitialTimeout
 lmt_settings.h, 27
setResponseWaitTimeout
 lmt_settings.h, 27
settingsFileRead
 lmt_storage_manager.h, 33
setup
 lmt_sdk_api.h, 14
setUpLinkTimeout
 lmt_settings.h, 28
setUserBootOkMask
 lmt_common.h, 8
SomEvent
 lmt_som_event_emitter.h, 29

triggerDataPacking
 lmt_coap_manager.h, 6
triggerMailer
 lmt_coap_manager.h, 6

updatePeriod
 lmt_proto_handler.h, 13

WAIT_FOREVER
 lmt_coap_manager.h, 3
WAIT_ON_TIMEOUT
 lmt_coap_manager.h, 3