



LMT IoT Shortcut SDK API
2.0.0

1 File Index	1
1.1 File List	1
2 File Documentation	2
2.1 lmt_coap_manager.h File Reference	2
2.1.1 Macro Definition Documentation	3
2.1.1.1 APP_COAP_MAX_MSG_LEN	3
2.1.2 Enumeration Type Documentation	3
2.1.2.1 MailerWaitModes	3
2.1.3 Function Documentation	3
2.1.3.1 getDeviceSN()	3
2.1.3.2 getMailerWaitMode()	4
2.1.3.3 getNetworkQuality()	4
2.1.3.4 getPacketCounter()	4
2.1.3.5 getPacketCounterLimit()	4
2.1.3.6 isModemInitialized()	5
2.1.3.7 isSocketConnected()	5
2.1.3.8 modemShutdown()	5
2.1.3.9 resetPacketCounter()	5
2.1.3.10 sendEventCmdRes()	5
2.1.3.11 setMailerWaitMode()	5
2.1.3.12 setPacketCounter()	6
2.1.3.13 setPacketCounterLimit()	6
2.1.3.14 setRawData()	6
2.1.3.15 triggerDataPacking()	6
2.1.3.16 triggerMailer()	7
2.2 lmt_common.h File Reference	7
2.2.1 Macro Definition Documentation	7
2.2.1.1 FIRST_USER_STATUS_BIT	7
2.2.1.2 LAST_USER_STATUS_BIT	7
2.2.2 Function Documentation	7
2.2.2.1 checkBootOkMask()	7
2.2.2.2 criticalError()	8
2.2.2.3 resetStatusBit()	8
2.2.2.4 setBootOkBit()	8
2.2.2.5 setUserBootOkMask()	8
2.3 lmt_monitor.h File Reference	9
2.3.1 Function Documentation	9
2.3.1.1 logResetReason()	9
2.3.1.2 saveResetRegister()	9
2.4 lmt_proto_handler.h File Reference	9
2.4.1 Macro Definition Documentation	10

2.4.1.1 I_TAPE	10
2.4.1.2 MAX_ACTION_PARAMETERS_SIZE	10
2.4.1.3 MAX_COLUMNS_COUNT	10
2.4.1.4 MAX_PERIODS_COUNT	11
2.4.1.5 MAX_TAPE_COUNT	11
2.4.1.6 MAX_TRACKS_COUNT	11
2.4.2 Function Documentation	11
2.4.2.1 addColumnToTape()	11
2.4.2.2 decodeMessage()	11
2.4.2.3 dumpMemory()	11
2.4.2.4 encodeMessage()	12
2.4.2.5 getEncodedMsgBuffer()	12
2.4.2.6 getEncodedMsgLen()	12
2.4.2.7 getLastPeriod()	12
2.4.2.8 getTapeRecordsCount()	13
2.4.2.9 isCompressionCheckRequired()	13
2.4.2.10 isDataChanged()	13
2.4.2.11 isUdpPacketFull()	14
2.4.2.12 restartMeasurements()	14
2.4.2.13 rewindTape()	14
2.4.2.14 updatePeriod()	14
2.5 Imt_sdk_api.h File Reference	15
2.5.1 Function Documentation	15
2.5.1.1 ImtInit()	15
2.5.1.2 loop()	15
2.5.1.3 setup()	15
2.6 Imt_settings.h File Reference	15
2.6.1 Enumeration Type Documentation	18
2.6.1.1 ActiveSim	18
2.6.1.2 LogLevel	18
2.6.2 Function Documentation	18
2.6.2.1 disableSerialLog()	18
2.6.2.2 enableSerialLog()	19
2.6.2.3 getActiveSim()	19
2.6.2.4 getCoapDeviceName()	19
2.6.2.5 getCoapServerHostname()	19
2.6.2.6 getCoapServerPort()	20
2.6.2.7 getCoapTxFileResource()	20
2.6.2.8 getCoapTxFwResource()	20
2.6.2.9 getCoapTxResource()	20
2.6.2.10 getFileUIRetries()	21
2.6.2.11 getLogFileMaxSize()	21

2.6.2.12	getLogLevel()	21
2.6.2.13	getLogRotationFrequency()	21
2.6.2.14	getLTEConnectionTimeout()	22
2.6.2.15	getMaxResendAttempts()	22
2.6.2.16	getMaxResendTimeout()	22
2.6.2.17	getModemMode()	22
2.6.2.18	getModemModePreference()	23
2.6.2.19	getNoPsmUplinkTimeout()	23
2.6.2.20	getNumOfLogFiles()	23
2.6.2.21	getPsmRatTimeout()	23
2.6.2.22	getResendPacketInitialTimeout()	24
2.6.2.23	getResponseWaitTimeout()	24
2.6.2.24	getUIDataMode()	24
2.6.2.25	getUplinkTimeout()	24
2.6.2.26	isDeviceBatteryPowered()	25
2.6.2.27	printCoap()	25
2.6.2.28	scanForCoapKeys()	25
2.6.2.29	setActiveSim()	25
2.6.2.30	setCoapServerHostname()	25
2.6.2.31	setCoapServerPort()	26
2.6.2.32	setCoapTxFileResource()	26
2.6.2.33	setCoapTxFwResource()	26
2.6.2.34	setCoapTxResource()	26
2.6.2.35	setFileUIRetries()	27
2.6.2.36	setLogFileMaxSize()	27
2.6.2.37	setLogLevel()	27
2.6.2.38	setLogRotationFrequency()	27
2.6.2.39	setLTEConnectionTimeout()	28
2.6.2.40	setMaxResendAttempts()	28
2.6.2.41	setMaxResendTimeout()	28
2.6.2.42	setModemMode()	29
2.6.2.43	setModemModePreference()	29
2.6.2.44	setNoPsmUplinkTimeout()	29
2.6.2.45	setNumOfLogFiles()	30
2.6.2.46	setPowerOption()	30
2.6.2.47	setPsmRatTimeout()	30
2.6.2.48	setResendPacketInitialTimeout()	31
2.6.2.49	setResponseWaitTimeout()	31
2.6.2.50	setUIDataMode()	31
2.6.2.51	setUplinkTimeout()	32
2.7	lmt_som_event_emitter.h File Reference	32
2.7.1	Typedef Documentation	33

2.7.1.1 EventHandler	33
2.7.2 Enumeration Type Documentation	33
2.7.2.1 SomEvent	33
2.7.3 Function Documentation	34
2.7.3.1 handleSomEvent()	34
2.8 lmt_storage_manager.h File Reference	34
2.8.1 Function Documentation	35
2.8.1.1 checkFwUpgradeStatus()	35
2.8.1.2 eraseFlash()	35
2.8.1.3 logError()	35
2.8.1.4 logInfo()	36
2.8.1.5 logInfoFormatted()	36
2.8.1.6 logStringHex()	36
2.8.1.7 logWarning()	37
2.8.1.8 saveSettings()	37
2.8.1.9 settingsFileRead()	37
Index	38

Chapter 1

File Index

1.1 File List

Here is a list of all files with brief descriptions:

lmt_coap_manager.h	2
lmt_common.h	7
lmt_monitor.h	9
lmt_proto_handler.h	9
lmt_sdk_api.h	15
lmt_settings.h	15
lmt_som_event_emitter.h	32
lmt_storage_manager.h	34

Chapter 2

File Documentation

2.1 lmt_coap_manager.h File Reference

Macros

- `#define APP_COAP_MAX_MSG_LEN 1280`

Enumerations

- `enum MailerWaitModes { WAIT_ON_TIMEOUT = 0 , WAIT_FOREVER = 1 }`
Enum for mailer wait control.

Functions

- `void getDeviceSN (char *sn_buffer, size_t *buffer_size)`
Reads device serial number (SN).
- `bool isSocketConnected (void)`
Checks if the device is currently connected to the IoT network.
- `bool isModemInitialized (void)`
Checks if the modem is initialized.
- `MailerWaitModes getMailerWaitMode (void)`
Returns the mailer wait mode.
- `void setMailerWaitMode (MailerWaitModes mode)`
Sets the mailer wait mode.
- `uint32_t getPacketCounter (void)`
Retrieves the current packet counter value.
- `void setPacketCounter (uint32_t counter)`
Sets the packet counter to a specific value.
- `void resetPacketCounter (void)`
Resets the packet counter to zero.
- `uint32_t getPacketCounterLimit (void)`
Retrieves the packet counter limit that will trigger the radio data update.
- `void setPacketCounterLimit (uint32_t limit)`
Sets a new packet counter limit that will trigger the radio data update.
- `int getNetworkQuality (int32_t *rsrp, int32_t *rsrq, int32_t *snr)`

- Function gets the cached signal quality from the modem.*
- void triggerDataPacking (bool set_include_radio_parms)
Enable packer thread to create a CoAP message.
- void triggerMailer (bool trigger_radio_pata_packing)
Enable mailer thread; first data packet containing radio data can be created.
- int setRawData (uint8_t *raw_data, uint16_t raw_data_len, bool upload)
Set raw data pointer and length.
- void modemShutdown (void)
Function to close the socket and power off the modem.
- void sendEventCmdRes (int res)
Set and send terminal command result.

2.1.1 Macro Definition Documentation

2.1.1.1 APP_COAP_MAX_MSG_LEN

```
#define APP_COAP_MAX_MSG_LEN 1280
```

2.1.2 Enumeration Type Documentation

2.1.2.1 MailerWaitModes

```
enum MailerWaitModes
```

Enum for mailer wait control.

Enumerator

WAIT_ON_TIMEOUT	
WAIT_FOREVER	

```
00033 {
00034     WAIT_ON_TIMEOUT = 0,
00035     WAIT_FOREVER    = 1
00036 } MailerWaitModes;
```

2.1.3 Function Documentation

2.1.3.1 getDeviceSN()

```
void getDeviceSN (
    char * sn_buffer,
    size_t * buffer_size)
```

Reads device serial number (SN).

Parameters

<i>sn_buffer</i>	Pointer to store the SN.
<i>buffer_size</i>	Pointer to buffer size; updated with actual SN length.

2.1.3.2 getMailerWaitMode()

```
MailerWaitModes getMailerWaitMode (  
    void )
```

Returns the mailer wait mode.

Returns

WAIT_ON_TIMEOUT (false) if the mailer waits on timeout, WAIT_FOREVER (true) if the mailer has to be started by user

2.1.3.3 getNetworkQuality()

```
int getNetworkQuality (  
    int32_t * rsrp,  
    int32_t * rsrq,  
    int32_t * snr)
```

Function gets the cached signal quality from the modem.

Parameters

<i>rsrp</i>	Pointer to store the RSRP value
<i>rsrq</i>	Pointer to store the RSRQ value
<i>snr</i>	Pointer to store the SNR value

Returns

0 if values values, -EINVAL otherwise

2.1.3.4 getPacketCounter()

```
uint32_t getPacketCounter (  
    void )
```

Retrieves the current packet counter value.

Returns

Current packet counter value.

2.1.3.5 getPacketCounterLimit()

```
uint32_t getPacketCounterLimit (  
    void )
```

Retrieves the packet counter limit that will trigger the radio data update.

Returns

The maximum allowed packet counter value.

2.1.3.6 isModemInitialized()

```
bool isModemInitialized (
    void )
```

Checks if the modem is initialized.

Returns

true if the modem is initialized, false otherwise.

2.1.3.7 isSocketConnected()

```
bool isSocketConnected (
    void )
```

Checks if the device is currently connected to the IoT network.

Returns

true if the device is connected, false otherwise.

2.1.3.8 modemShutdown()

```
void modemShutdown (
    void )
```

Function to close the socket and power off the modem.

2.1.3.9 resetPacketCounter()

```
void resetPacketCounter (
    void )
```

Resets the packet counter to zero.

2.1.3.10 sendEventCmdRes()

```
void sendEventCmdRes (
    int res)
```

Set and send terminal command result.

Parameters

<i>res</i>	Result of the command, 0 if successful, negative value otherwise
------------	--

2.1.3.11 setMailerWaitMode()

```
void setMailerWaitMode (
    MailerWaitModes mode)
```

Sets the mailer wait mode.

Parameters

<i>mode</i>	WAIT_ON_TIMEOUT (false) if the mailer has to wait on timeout, WAIT_FOREVER (true) if the user controls the mailer start
-------------	---

2.1.3.12 setPacketCounter()

```
void setPacketCounter (
    uint32_t counter)
```

Sets the packet counter to a specific value.

Parameters

<i>counter</i>	The new value for the packet counter.
----------------	---------------------------------------

2.1.3.13 setPacketCounterLimit()

```
void setPacketCounterLimit (
    uint32_t limit)
```

Sets a new packet counter limit that will trigger the radio data update.

Parameters

<i>limit</i>	The new upper limit for the packet counter.
--------------	---

2.1.3.14 setRawData()

```
int setRawData (
    uint8_t * raw_data,
    uint16_t raw_data_len,
    bool upload)
```

Set raw data pointer and length.

Parameters

<i>raw_data</i>	Pointer to raw data buffer
<i>raw_data_len</i>	Length of the raw data
<i>upload</i>	Flag to trigger mailer for immediate upload of raw data

Returns

0 on success, negative error code on fail

2.1.3.15 triggerDataPacking()

```
void triggerDataPacking (
    bool set_include_radio_parms)
```

Enable packer thread to create a CoAP message.

Parameters

<code>set_include_radio_parms</code>	when set, radio data will be added
--------------------------------------	------------------------------------

2.1.3.16 triggerMailer()

```
void triggerMailer (
    bool trigger_radio_pata_packing)
```

Enable mailer thread; first data packet containing radio data can be created.

Parameters

<code>trigger_radio_pata_packing</code>	when set, radio data packet will be added
---	---

2.2 Imt_common.h File Reference**Macros**

- `#define FIRST_USER_STATUS_BIT 16`
- `#define LAST_USER_STATUS_BIT 31`

Functions

- `void criticalError (void)`
Calls assert and triggers system reset in case of critical error.
- `bool checkBootOkMask (uint32_t mask)`
Returns the flag if the given mask is set in BootOK status.
- `void setUserBootOkMask (uint32_t mask)`
Set user app boot ok mask.
- `void setBootOkBit (uint32_t bit)`
Set appropriate status bit.
- `void resetStatusBit (uint32_t bit)`
Reset appropriate status bit.

2.2.1 Macro Definition Documentation**2.2.1.1 FIRST_USER_STATUS_BIT**

```
#define FIRST_USER_STATUS_BIT 16
```

2.2.1.2 LAST_USER_STATUS_BIT

```
#define LAST_USER_STATUS_BIT 31
```

2.2.2 Function Documentation**2.2.2.1 checkBootOkMask()**

```
bool checkBootOkMask (
    uint32_t mask)
```

Returns the flag if the given mask is set in BootOK status.

Parameters

<i>mask</i>	The mask of the interested flags
-------------	----------------------------------

Returns

true if all flags are set, false otherwise

2.2.2.2 criticalError()

```
void criticalError (  
    void )
```

Calls assert and triggers system reset in case of critical error.

2.2.2.3 resetStatusBit()

```
void resetStatusBit (  
    uint32_t bit)
```

Reset appropriate status bit.

Parameters

<i>bit</i>	The number of bit that has to be reset
------------	--

2.2.2.4 setBootOkBit()

```
void setBootOkBit (  
    uint32_t bit)
```

Set appropriate status bit.

Parameters

<i>bit</i>	The number of bit that has to be set
------------	--------------------------------------

2.2.2.5 setUserBootOkMask()

```
void setUserBootOkMask (  
    uint32_t mask)
```

Set user app boot ok mask.

Parameters

<i>mask</i>	The mask of the interested flags
-------------	----------------------------------

2.3 Imt_monitor.h File Reference

Functions

- void saveResetRegister (void)
Saves the reset reason register for analysis.
- void logResetReason (void)
Analyses and logs the reset reason[s].

2.3.1 Function Documentation

2.3.1.1 logResetReason()

```
void logResetReason (  
    void )
```

Analyses and logs the reset reason[s].

2.3.1.2 saveResetRegister()

```
void saveResetRegister (  
    void )
```

Saves the reset reason register for analysis.

2.4 Imt_proto_handler.h File Reference

Macros

- #define MAX_TRACKS_COUNT 12
- #define MAX_PERIODS_COUNT 3
- #define MAX_COLUMNS_COUNT 50
- #define MAX_TAPE_COUNT 1
- #define MAX_ACTION_PARAMETERS_SIZE 256
- #define I_TAPE 0

Functions

- void dumpMemory (uint8_t *ptr, uint16_t size)
Dumps in HEX the memory region at the given address of the given size.
- bool isDataChanged (void)
Returns flag signalling that data is updated in comparison to the last encoded message.
- void updatePeriod (uint8_t i_tape, uint32_t value)
Function to add a new period to the Periods array of a given Tape. During operation first add the period, then measurement. The duplicate value entries will be not added. The entries without measurements will be overwritten. On overflow it will reset the Periods array. Corrects also the Columns_count if Columns_count >= MAX_COLUMNS_COUNT.
- uint32_t getLastPeriod (uint8_t i_tape)
Returns the last defined period of the Tape instance given by pointer.
- int addColumnToTape (uint8_t i_tape, uint32_t period, int32_t *p_measurements)
Adds a measurements column and its period to the given Tape.
- pb_size_t getTapeRecordsCount (uint8_t i_tape)
Returns actual column count in Tape.
- void rewindTape (uint8_t i_tape)
Resets the Tape keeping the last period entry.
- void restartMeasurements (void)
Clear sensor measurements keeping the last measurement periods.
- bool encodeMessage (void)
Encodes uplink message.
- uint16_t getEncodedMsgLen (void)
Get encoded message length.
- const uint8_t * getEncodedMsgBuffer (void)
Get pointer to encoded message buffer.
- bool isCompressionCheckRequired (void)
Checks if the data will fit UDP packet with no compression.
- bool isUdpPacketFull (void)
Checks if the UDP packet is full.
- bool decodeMessage (const uint8_t *p_buffer)
Decodes downlink message.

2.4.1 Macro Definition Documentation

2.4.1.1 I_TAPE

```
#define I_TAPE 0
```

2.4.1.2 MAX_ACTION_PARAMETERS_SIZE

```
#define MAX_ACTION_PARAMETERS_SIZE 256
```

2.4.1.3 MAX_COLUMNS_COUNT

```
#define MAX_COLUMNS_COUNT 50
```

2.4.1.4 MAX_PERIODS_COUNT

```
#define MAX_PERIODS_COUNT 3
```

2.4.1.5 MAX_TAPE_COUNT

```
#define MAX_TAPE_COUNT 1
```

2.4.1.6 MAX_TRACKS_COUNT

```
#define MAX_TRACKS_COUNT 12
```

2.4.2 Function Documentation

2.4.2.1 addColumnToTape()

```
int addColumnToTape (  
    uint8_t i_tape,  
    uint32_t period,  
    int32_t * p_measurements)
```

Adds a measurements column and its period to the given Tape.

Parameters

<i>i_tape</i>	the Tape index
<i>period</i>	the period value
<i>p_measurements</i>	pointer to the measurements array in count of MAX_TRACKS_COUNT

Returns

number of remaining empty columns, -EINVAL if *i_tape* is out of range

2.4.2.2 decodeMessage()

```
bool decodeMessage (  
    const uint8_t * p_buffer)
```

Decodes downlink message.

Parameters

<i>p_buffer</i>	pointer to incoming message
-----------------	-----------------------------

Returns

success flag

2.4.2.3 dumpMemory()

```
void dumpMemory (  
    uint8_t * ptr,  
    uint16_t size)
```

Dumps in HEX the memory region at the given address of the given size.

Parameters

<i>*ptr</i>	The starting memory address
<i>size</i>	The size of the memory dump

2.4.2.4 encodeMessage()

```
bool encodeMessage (  
    void )
```

Encodes uplink message.

Returns

success flag

2.4.2.5 getEncodedMsgBuffer()

```
const uint8_t * getEncodedMsgBuffer (  
    void )
```

Get pointer to encoded message buffer.

Returns

Constant pointer to encoded message buffer

2.4.2.6 getEncodedMsgLen()

```
uint16_t getEncodedMsgLen (  
    void )
```

Get encoded message length.

Returns

Current encoded message length

2.4.2.7 getLastPeriod()

```
uint32_t getLastPeriod (  
    uint8_t i_tape)
```

Returns the last defined period of the Tape instance given by pointer.

Parameters

<i>i_tape</i>	the Tape index
---------------	----------------

Returns

the last defined period or 0 if period is not set

2.4.2.8 getTapeRecordsCount()

```
pb_size_t getTapeRecordsCount (
    uint8_t i_tape)
```

Returns actual column count in Tape.

Parameters

<i>i_tape</i>	the Tape index
---------------	----------------

Returns

Column count in Tape

2.4.2.9 isCompressionCheckRequired()

```
bool isCompressionCheckRequired (
    void )
```

Checks if the data will fit UDP packet with no compression.

Returns

true if data will not fit, false otherwise

2.4.2.10 isDataChanged()

```
bool isDataChanged (
    void )
```

Returns flag signalling that data is updated in comparison to the last encoded message.

Returns

A flag signalling that data had been changed

2.4.2.11 isUdpPacketFull()

```
bool isUdpPacketFull (
    void )
```

Checks if the UDP packet is full.

Returns

true if full, false otherwise

2.4.2.12 restartMeasurements()

```
void restartMeasurements (
    void )
```

Clear sensor measurements keeping the last measurement periods.

2.4.2.13 rewindTape()

```
void rewindTape (
    uint8_t i_tape)
```

Resets the Tape keeping the last period entry.

Parameters

<i>i_tape</i>	the Tape index
---------------	----------------

2.4.2.14 updatePeriod()

```
void updatePeriod (
    uint8_t i_tape,
    uint32_t value)
```

Function to add a new period to the Periods array of a given Tape. During operation first add the period, then measurement. The duplicate value entries will be not added. The entries without measurements will be overwritten. On overflow it will reset the Periods array. Corrects also the Columns_count if Columns_count >= MAX_COLUMNS -> _COUNT.

Parameters

<i>i_tape</i>	the Tape index
<i>value</i>	the period value

2.5 lmt_sdk_api.h File Reference

Functions

- void lmtInit (void)
Initializes the SDK.
- void setup (void)
User application setup code.
- void loop (void)
User application main control loop.

2.5.1 Function Documentation

2.5.1.1 lmtInit()

```
void lmtInit (  
    void )
```

Initializes the SDK.

2.5.1.2 loop()

```
void loop (  
    void )
```

User application main control loop.

2.5.1.3 setup()

```
void setup (  
    void )
```

User application setup code.

2.6 lmt_settings.h File Reference

Enumerations

- enum LogLevel { LOG_ERRORS = 0 , LOG_WARNINGS , LOG_INFORMATIVE }
Log level options for system logging.
- enum ActiveSim { ACTIVATE_ESIM = 0 , ACTIVATE_SIM = 1 }
Enum for active SIM control.

Functions

- void printCoap (void)
Prints coap structure.
- int scanForCoapKeys (const uint8_t *p_coap_data, unsigned int size)
Scans a buffer for COAP key/value pairs stored as C strings (key\0value\0).
- void setCoapServerPort (uint16_t port)
Set the COAP server port number.
- void setCoapTxResource (const char *resource)
Set the COAP transmission resource path.
- void setCoapTxFileResource (const char *resource)
Set the COAP file transmission resource path.
- void setCoapTxFwResource (const char *resource)
Set the COAP firmware transmission resource path.
- void setCoapServerHostname (const char *hostname)
Set the hostname of the main COAPS server.
- uint16_t getCoapServerPort (void)
Get the currently configured COAP server port.
- const char * getCoapTxResource (void)
Get the configured COAP transmission resource path.
- const char * getCoapTxFileResource (void)
Get the configured COAP file transmission resource path.
- const char * getCoapTxFwResource (void)
Get the configured COAP firmware transmission resource path.
- void getCoapDeviceName (char *device_name, unsigned *len)
Get the configured device name used in COAP.
- const char * getCoapServerHostname (void)
Get the configured main COAPS server hostname.
- void setPowerOption (bool battery_powered_flag)
Sets devices power option flag; it has to be set before the lmtInit(). By default the device counts as battery powered.
- int setLogFileMaxSize (int32_t size)
Set the maximum size of the log file.
- int setLTEConnectionTimeout (uint16_t timeout)
Set network connection timeout.
- int setUplinkTimeout (uint16_t timeout)
Set the device uplink timeout.
- int setNoPsmUplinkTimeout (uint16_t timeout)
Set the device uplink timeout when PSM not available.
- int setResendPacketInitialTimeout (uint8_t timeout)
Set the initial timeout for resending packets.
- int setMaxResendTimeout (uint8_t timeout)
Set the maximum timeout for resending packets.
- int setMaxResendAttempts (uint8_t attempts)
Set the maximum number of resend attempts.
- int setLogRotationFrequency (uint8_t frequency)
Set the frequency of log rotation checks.
- int setResponseWaitTimeout (uint8_t timeout)
Set the CoAP response wait timeout.
- int setFileUIRetries (uint8_t retries)
Set the number of retries for file uploads.
- int setNumOfLogFiles (uint8_t file_count)

- Set the maximum number of log files on flash before starting file rotation.*

 - int setLogLevel (LogLevel level)

Set the log level for the application.
- int setActiveSim (ActiveSim sim_source)

Sets the current SIM source.
- int setUIDataMode (uint8_t mode)

Sets the current data upload mode.
- int setModemMode (unsigned mode)

Set modem operating mode. Only has effect if modem is initialized after this setting is set.
- int setModemModePreference (unsigned preference)

Set modem LTE mode preference. Only has effect if modem mode is set to 2 (LTE-M & NB-IoT) and modem is initialized after this setting is set.
- int setPsmRatTimeout (unsigned timeout_seconds)

Set the PSM RAT (Requested Active Time) timeout value. Setting will only take effect if modem is initialized after this setting is set.
- bool isDeviceBatteryPowered (void)

Reads devices power option flag: true for battery powered devices. By default the device counts as battery powered (this function returns true).
- int32_t getLogFileMaxSize (void)

Get the maximum size of the log file.
- uint16_t getLTEConnectionTimeout (void)

Get network connection timeout.
- uint16_t getUplinkTimeout (void)

Get the device uplink timeout.
- uint16_t getNoPsmUplinkTimeout (void)

Get the device uplink timeout when no PSM available.
- uint8_t getResendPacketInitialTimeout (void)

Get the initial timeout for resending packets.
- uint8_t getMaxResendTimeout (void)

Get the maximum timeout for resending packets.
- uint8_t getMaxResendAttempts (void)

Get the maximum number of resend attempts.
- uint8_t getLogRotationFrequency (void)

Get the frequency of log rotation checks.
- uint8_t getResponseWaitTimeout (void)

Get the CoAP response wait timeout.
- uint8_t getFileUIRetries (void)

Get the number of retries for file uploads.
- uint8_t getNumOfLogFiles (void)

Get the maximum number of log file count in flash.
- LogLevel getLogLevel (void)

Get the log level for the application.
- int getActiveSim (ActiveSim *sim_source)

Returns the current SIM source.
- uint8_t getUIDataMode (void)

Get the current data upload mode.
- unsigned getModemMode (void)

Get modem operating mode.
- unsigned getModemModePreference (void)

Get modem LTE mode preference. Has effect only if modem mode is set to 2 (LTE-M & NB-IoT).
- unsigned getPsmRatTimeout (char *rat_string_buffer)

Get the PSM RAT timeout value and its T3324 binary string representation.

- uint8_t disableSerialLog (void)

Disable serial logging output by suspending the UART device.

- uint8_t enableSerialLog (void)

Enable serial logging output by resuming the UART device.

2.6.1 Enumeration Type Documentation

2.6.1.1 ActiveSim

```
enum ActiveSim
```

Enum for active SIM control.

Enumerator

ACTIVATE_ESIM	
ACTIVATE_SIM	

```
00040 {
00041     ACTIVATE_ESIM = 0,
00042     ACTIVATE_SIM  = 1
00043 } ActiveSim;
```

2.6.1.2 LogLevel

```
enum LogLevel
```

Log level options for system logging.

This enum defines the available log levels for controlling the verbosity of saved system logs.

Enumerator

LOG_ERRORS	
LOG_WARNINGS	
LOG_INFORMATIVE	

```
00030 {
00031     LOG_ERRORS = 0,
00032     LOG_WARNINGS,
00033     LOG_INFORMATIVE
00034 } LogLevel;
```

2.6.2 Function Documentation

2.6.2.1 disableSerialLog()

```
uint8_t disableSerialLog (
    void )
```

Disable serial logging output by suspending the UART device.

Suspends the UART device using power management to disable serial output for logging and debugging. This can help reduce power consumption when serial output is not needed.

Returns

0 on success, negative error code on failure. Returns -EALREADY if the device is already suspended (not treated as error).

2.6.2.2 enableSerialLog()

```
uint8_t enableSerialLog (  
    void )
```

Enable serial logging output by resuming the UART device.

Resumes the UART device using power management to enable serial output for logging and debugging. This allows real-time monitoring of device operation after the UART was previously suspended.

Returns

0 on success, negative error code on failure. Returns -EALREADY if the device is already active (not treated as error).

2.6.2.3 getActiveSim()

```
int getActiveSim (  
    ActiveSim * sim_source)
```

Returns the current SIM source.

Parameters

<i>sim_source</i>	Pointer to the source of the SIM
-------------------	----------------------------------

Returns

0 on success, negative error code on failure.

2.6.2.4 getCoapDeviceName()

```
void getCoapDeviceName (  
    char * device_name,  
    unsigned * len)
```

Get the configured device name used in COAP.

Parameters

<i>device_name</i>	Pointer to a buffer where the device name will be stored.
<i>len</i>	Length pointer holds in/out buffer size.

2.6.2.5 getCoapServerHostname()

```
const char * getCoapServerHostname (  
    void )
```

Get the configured main COAPS server hostname.

Returns

Null-terminated string with the server hostname.

2.6.2.6 getCoapServerPort()

```
uint16_t getCoapServerPort (  
    void )
```

Get the currently configured COAP server port.

Returns

Server port as uint16_t.

2.6.2.7 getCoapTxFileResource()

```
const char * getCoapTxFileResource (  
    void )
```

Get the configured COAP file transmission resource path.

Returns

Null-terminated string representing the file resource path.

2.6.2.8 getCoapTxFwResource()

```
const char * getCoapTxFwResource (  
    void )
```

Get the configured COAP firmware transmission resource path.

Returns

Null-terminated string representing the firmware resource path.

2.6.2.9 getCoapTxResource()

```
const char * getCoapTxResource (  
    void )
```

Get the configured COAP transmission resource path.

Returns

Null-terminated string representing the resource path.

2.6.2.10 getFileUIRetries()

```
uint8_t getFileUIRetries (  
    void )
```

Get the number of retries for file uploads.

Returns

Number of retries for file uploads.

2.6.2.11 getLogFileMaxSize()

```
int32_t getLogFileMaxSize (  
    void )
```

Get the maximum size of the log file.

Returns

Maximum size of the log file in bytes.

2.6.2.12 getLogLevel()

```
LogLevel getLogLevel (  
    void )
```

Get the log level for the application.

Returns

Log level for the application.

2.6.2.13 getLogRotationFrequency()

```
uint8_t getLogRotationFrequency (  
    void )
```

Get the frequency of log rotation checks.

Returns

Frequency of log rotation checks in wakeup cycles.

2.6.2.14 getLTEConnectionTimeout()

```
uint16_t getLTEConnectionTimeout (
    void )
```

Get network connection timeout.

Returns

Device network connection timeout in seconds.

2.6.2.15 getMaxResendAttempts()

```
uint8_t getMaxResendAttempts (
    void )
```

Get the maximum number of resend attempts.

Returns

Maximum number of resend attempts before the socket is closed.

2.6.2.16 getMaxResendTimeout()

```
uint8_t getMaxResendTimeout (
    void )
```

Get the maximum timeout for resending packets.

Returns

Maximum timeout for resending packets in hours.

2.6.2.17 getModemMode()

```
unsigned getModemMode (
    void )
```

Get modem operating mode.

Returns

0 on success, negative error code on failure. 0 for LTE-M; 1 for NB-IoT; 2 for LTE-M & NB-IoT

2.6.2.18 getModemModePreference()

```
unsigned getModemModePreference (
    void )
```

Get modem LTE mode preference. Has effect only if modem mode is set to 2 (LTE-M & NB-IoT).

Returns

Modem LTE mode preference 0 no preference; 1 LTE-M preferred (fallback to NB-IoT if LTE-M not available); 2 NB-IoT preferred (fallback to LTE-M if NB-IoT not available); 3 Network priorities override system; prefer LTE-M when equal priority. 4 Network priorities override system; prefer NB-IoT when equal priority.

2.6.2.19 getNoPsmUplinkTimeout()

```
uint16_t getNoPsmUplinkTimeout (
    void )
```

Get the device uplink timeout when no PSM available.

Returns

Device uplink timeout when PSM not available in hours.

2.6.2.20 getNumOfLogFiles()

```
uint8_t getNumOfLogFiles (
    void )
```

Get the maximum number of log file count in flash.

Returns

Number of maximum count of log files stored in flash.

2.6.2.21 getPsmRatTimeout()

```
unsigned getPsmRatTimeout (
    char * rat_string_buffer)
```

Get the PSM RAT timeout value and its T3324 binary string representation.

Returns the current PSM RAT timeout in seconds and generates the corresponding T3324 binary string for use with `lte_lc_psm_param_set()`.

Parameters

<code>rat_string_buffer</code>	Output buffer for the 8-bit binary string (must be at least 9 bytes)
--------------------------------	--

Returns

Current PSM RAT timeout in seconds

2.6.2.22 getResendPacketInitialTimeout()

```
uint8_t getResendPacketInitialTimeout (
    void )
```

Get the initial timeout for resending packets.

Returns

Initial timeout for resending packets in minutes.

2.6.2.23 getResponseWaitTimeout()

```
uint8_t getResponseWaitTimeout (
    void )
```

Get the CoAP response wait timeout.

Returns

Timeout for waiting for CoAP response in seconds.

2.6.2.24 getUIDataMode()

```
uint8_t getUlDataMode (
    void )
```

Get the current data upload mode.

Returns

Data upload mode - 0 for normal mode, 1 for raw mode (unformatted data)

2.6.2.25 getUplinkTimeout()

```
uint16_t getUplinkTimeout (
    void )
```

Get the device uplink timeout.

Returns

Device uplink timeout in minutes.

2.6.2.26 isDeviceBatteryPowered()

```
bool isDeviceBatteryPowered (  
    void )
```

Reads devices power option flag: true for battery powered devices. By default the device counts as battery powered (this function returns true).

2.6.2.27 printCoap()

```
void printCoap (  
    void )
```

Prints coap structure.

2.6.2.28 scanForCoapKeys()

```
int scanForCoapKeys (  
    const uint8_t * p_coap_data,  
    unsigned int size)
```

Scans a buffer for COAP key/value pairs stored as C strings (key\0value\0).

Parameters

<i>p_coap_data</i>	a Pointer
<i>size</i>	Size to scan.

Returns

0 on success, negative error code on failure.

2.6.2.29 setActiveSim()

```
int setActiveSim (  
    ActiveSim sim_source)
```

Sets the current SIM source.

Parameters

<i>sim_source</i>	Source of the SIM
-------------------	-------------------

Returns

0 on success, negative error code on failure.

2.6.2.30 setCoapServerHostname()

```
void setCoapServerHostname (  
    const char * hostname)
```

Set the hostname of the main COAPS server.

Parameters

<i>hostname</i>	Null-terminated string with the server's hostname or IP address.
-----------------	--

2.6.2.31 setCoapServerPort()

```
void setCoapServerPort (  
    uint16_t port)
```

Set the COAP server port number.

Parameters

<i>port</i>	COAP server port (typically 5683 for COAP, 5684 for COAPS).
-------------	---

2.6.2.32 setCoapTxFileResource()

```
void setCoapTxFileResource (  
    const char * resource)
```

Set the COAP file transmission resource path.

Parameters

<i>resource</i>	Null-terminated string for the file resource (e.g. "upload").
-----------------	---

2.6.2.33 setCoapTxFwResource()

```
void setCoapTxFwResource (  
    const char * resource)
```

Set the COAP firmware transmission resource path.

Parameters

<i>resource</i>	Null-terminated string for the firmware update resource.
-----------------	--

2.6.2.34 setCoapTxResource()

```
void setCoapTxResource (  
    const char * resource)
```

Set the COAP transmission resource path.

Parameters

<i>resource</i>	Null-terminated string representing the resource path (e.g. "sensor/data").
-----------------	---

2.6.2.35 setFileUIRetries()

```
int setFileUIRetries (  
    uint8_t retries)
```

Set the number of retries for file uploads.

Parameters

<i>retries</i>	Number of retries for file uploads. 1 <= retries <= 10.
----------------	---

Returns

0 on success, -EINVAL otherwise.

2.6.2.36 setLogFileMaxSize()

```
int setLogFileMaxSize (  
    int32_t size)
```

Set the maximum size of the log file.

Parameters

<i>size</i>	Maximum size of the log file in bytes. 1024 (KB) <= size <= 1048576 (1MB).
-------------	--

Returns

0 on success, -EINVAL otherwise.

2.6.2.37 setLogLevel()

```
int setLogLevel (  
    LogLevel level)
```

Set the log level for the application.

Parameters

<i>level</i>	Log level for the application. LOG_ERRORS, LOG_WARNINGS, LOG_INFORMATIVE.
--------------	---

Returns

0 on success, -EINVAL otherwise.

2.6.2.38 setLogRotationFrequency()

```
int setLogRotationFrequency (  
    uint8_t frequency)
```

Set the frequency of log rotation checks.

Parameters

<i>frequency</i>	Frequency of log rotation checks in wakeup cycles. $1 \leq \text{frequency} \leq 50$.
------------------	--

Returns

0 on success, -EINVAL otherwise.

2.6.2.39 setLTEConnectionTimeout()

```
int setLTEConnectionTimeout (  
    uint16_t timeout)
```

Set network connection timeout.

Parameters

<i>timeout</i>	Device network connection timeout in seconds. $1 \text{ (sec)} \leq \text{timeout} \leq 1800 \text{ (30 min)}$.
----------------	--

Returns

0 on success, -EINVAL otherwise.

2.6.2.40 setMaxResendAttempts()

```
int setMaxResendAttempts (  
    uint8_t attempts)
```

Set the maximum number of resend attempts.

Parameters

<i>attempts</i>	Maximum number of resend attempts before the socket is closed. $1 \leq \text{attempts} \leq 10$.
-----------------	---

Returns

0 on success, -EINVAL otherwise.

2.6.2.41 setMaxResendTimeout()

```
int setMaxResendTimeout (  
    uint8_t timeout)
```

Set the maximum timeout for resending packets.

Parameters

<i>timeout</i>	Maximum timeout for resending packets in hours. 1 (h) <= timeout <= 24 (1d).
----------------	--

Returns

0 on success, -EINVAL otherwise.

2.6.2.42 setModemMode()

```
int setModemMode (
    unsigned mode)
```

Set modem operating mode. Only has effect if modem is initialized after this setting is set.

Parameters

<i>mode</i>	Set modem operating mode 0 for LTE-M; 1 for NB-IoT; 2 for LTE-M & NB-IoT (default)
-------------	--

Returns

0 on success, negative error code on failure.

2.6.2.43 setModemModePreference()

```
int setModemModePreference (
    unsigned preference)
```

Set modem LTE mode preference. Only has effect if modem mode is set to 2 (LTE-M & NB-IoT) and modem is initialized after this setting is set.

Parameters

<i>preference</i>	Set modem LTE mode preference 0 no preference; 1 LTE-M preferred (fallback to NB-IoT if LTE-M not available) (default); 2 NB-IoT preferred (fallback to LTE-M if NB-IoT not available); 3 Network priorities override system; prefer LTE-M when equal priority. 4 Network priorities override system; prefer NB-IoT when equal priority.
-------------------	--

Returns

0 on success, negative error code on failure.

2.6.2.44 setNoPsmUplinkTimeout()

```
int setNoPsmUplinkTimeout (
    uint16_t timeout)
```

Set the device uplink timeout when PSM not available.

Parameters

<i>timeout</i>	Device uplink timeout in hours 1 <= timeout <= 24 (hours).
----------------	--

Returns

0 on success, -EINVAL otherwise.

2.6.2.45 setNumOfLogFiles()

```
int setNumOfLogFiles (
    uint8_t file_count)
```

Set the maximum number of log files on flash before starting file rotation.

Parameters

<i>file_count</i>	Number of log files on flash. 1 <= file_count <= 20.
-------------------	--

Returns

0 on success, -EINVAL otherwise.

2.6.2.46 setPowerOption()

```
void setPowerOption (
    bool battery_powered_flag)
```

Sets devices power option flag; it has to be set before the lmtInit(). By default the device counts as battery powered.

Parameters

<i>battery_powered_flag</i>	power option flag: true for battery powered devices.
-----------------------------	--

2.6.2.47 setPsmRatTimeout()

```
int setPsmRatTimeout (
    unsigned timeout_seconds)
```

Set the PSM RAT (Requested Active Time) timeout value. Setting will only take effect if modem is initialized after this setting is set.

Valid values are determined by T3324 timer encoding limitations:

- 2 to 62 seconds: Even numbers only (2, 4, 6, 8, ..., 58, 60, 62) Encoded with unit 000 (2-second increments)
- 120 seconds: Special case (2 minutes) Encoded with unit 001 (1-minute increments)

IMPORTANT: Values from 64-118 seconds are NOT supported due to T3324 encoding gap. Values above 120 seconds are rejected.

Parameters

<i>timeout_seconds</i>	Desired timeout in seconds
------------------------	----------------------------

Returns

0 on success, -EINVAL if value is invalid, -ERANGE if value exceeds 120

2.6.2.48 setResendPacketInitialTimeout()

```
int setResendPacketInitialTimeout (  
    uint8_t timeout)
```

Set the initial timeout for resending packets.

Parameters

<i>timeout</i>	Initial timeout for resending packets in minutes. 1 (min) <= timeout <= 60 (1h).
----------------	--

Returns

0 on success, -EINVAL otherwise.

2.6.2.49 setResponseWaitTimeout()

```
int setResponseWaitTimeout (  
    uint8_t timeout)
```

Set the CoAP response wait timeout.

Parameters

<i>timeout</i>	Timeout for waiting for CoAP response in seconds. 1 <= timeout <= 60.
----------------	---

Returns

0 on success, -EINVAL otherwise.

2.6.2.50 setUIDataMode()

```
int setUIDataMode (  
    uint8_t mode)
```

Sets the current data upload mode.

Parameters

<i>mode</i>	Data upload mode - 0 for normal mode, 1 for raw mode (unformatted data)
-------------	---

Returns

0 on success, negative error code on failure.

2.6.2.51 setUplinkTimeout()

```
int setUplinkTimeout (
    uint16_t timeout)
```

Set the device uplink timeout.

Parameters

<i>timeout</i>	Device uplink timeout in minutes. 5 (min) <= timeout <= 1440 (24h).
----------------	---

Returns

0 on success, -EINVAL otherwise.

2.7 lmt_som_event_emitter.h File Reference**Typedefs**

- typedef void(* EventHandler) (void *p_data, int i_data)

Enumerations

- enum SomEvent {
 EVENT_DEVICE_INIT_OK , EVENT_LOGGER_INIT_OK , EVENT_PACKER_INIT_OK , EVENT_MAILER_INIT_OK
 ,
 EVENT_DROPPING_OLDEST , EVENT_PACKER_STARTED , EVENT_PACKING_FAILED , EVENT_ENQUEUE_FAILED
 ,
 EVENT_PACKER_DONE_OK , EVENT_UL_START , EVENT_UL_MAX_RETRY , EVENT_UL_RETRY ,
 EVENT_UL_DONE , EVENT_RRC_IDLE , EVENT_RRC_CONNECTED , EVENT_NETWORK_UP ,
 EVENT_NETWORK_DOWN , EVENT_MODEM_ON , EVENT_MODEM_OFF , EVENT_COAP_START ,
 EVENT_COAP_FAIL , EVENT_COAP_NOACK , EVENT_COAP_OK , EVENT_LOG_ERROR ,
 EVENT_LOG_WARNING , EVENT_LOG_INFO , EVENT_TERMINAL_CMD , EVENT_COUNT }

Events emitted by the IoT Shortcut SDK library.

Functions

- void handleSomEvent (SomEvent event, void *p_data, int i_data)

Centralized event handler for the library. This is a weak function that can be overridden by the user application.

2.7.1 Typedef Documentation

2.7.1.1 EventHandler

```
typedef void(* EventHandler) (void *p_data, int i_data)
```

2.7.2 Enumeration Type Documentation

2.7.2.1 SomEvent

```
enum SomEvent
```

Events emitted by the IoT Shortcut SDK library.

This enumeration defines all possible events that can be emitted by the library to notify the application about various system and application-level occurrences, such as initialization, uplink status, logging, and terminal commands.

Enumerator

EVENT_DEVICE_INIT_OK	Device initialization completed successfully.
EVENT_LOGGER_INIT_OK	Logger module initialized successfully.
EVENT_PACKER_INIT_OK	Packer module initialized successfully.
EVENT_MAILER_INIT_OK	Mailer module initialized successfully.
EVENT_DROPPING_OLDEST	Uplink queue is full, the oldest message(s) are dropped.
EVENT_PACKER_STARTED	Packer started.
EVENT_PACKING_FAILED	Data packing failed.
EVENT_ENQUEUE_FAILED	Packer failed to enqueue packet.
EVENT_PACKER_DONE_OK	Package created and enqueued successfully.
EVENT_UL_START	Uplink process started.
EVENT_UL_MAX_RETRY	Uplink retry limit reached.
EVENT_UL_RETRY	Uplink retry is being attempted.
EVENT_UL_DONE	Uplink completed.
EVENT_RRC_IDLE	RRC connection entered idle state.
EVENT_RRC_CONNECTED	RRC connection entered connected state.
EVENT_NETWORK_UP	Network connection established.
EVENT_NETWORK_DOWN	Network connection lost.
EVENT_MODEM_ON	Modem is actively consuming power.
EVENT_MODEM_OFF	Modem is powered off to save energy.
EVENT_COAP_START	COAP packet uplink started.
EVENT_COAP_FAIL	COAP packet uplink failed.
EVENT_COAP_NOACK	No ACK received for the COAP packet.
EVENT_COAP_OK	COAP packet uplink completed successfully.
EVENT_LOG_ERROR	An error log event occurred.
EVENT_LOG_WARNING	A warning log event occurred.
EVENT_LOG_INFO	An informational log event occurred.
EVENT_TERMINAL_CMD	A terminal command event occurred.
EVENT_COUNT	Event count.

```

00030 {
00031     EVENT_DEVICE_INIT_OK,
00032     EVENT_LOGGER_INIT_OK,
00033     EVENT_PACKER_INIT_OK,
00034     EVENT_MAILER_INIT_OK,
00035
00036     EVENT_DROPPING_OLDEST,
00037
00038     EVENT_PACKER_STARTED,
00039     EVENT_PACKING_FAILED,
00040     EVENT_ENQUEUE_FAILED,
00041     EVENT_PACKER_DONE_OK,
00042
00043     EVENT_UL_START,
00044     EVENT_UL_MAX_RETRY,
00045     EVENT_UL_RETRY,
00046     EVENT_UL_DONE,
00047
00048     EVENT_RRC_IDLE,
00049     EVENT_RRC_CONNECTED,
00050     EVENT_NETWORK_UP,
00051     EVENT_NETWORK_DOWN,
00052
00053     EVENT_MODEM_ON,
00054     EVENT_MODEM_OFF,
00055
00056     EVENT_COAP_START,
00057     EVENT_COAP_FAIL,
00058     EVENT_COAP_NOACK,
00059     EVENT_COAP_OK,
00060
00061     EVENT_LOG_ERROR,
00062     EVENT_LOG_WARNING,
00063     EVENT_LOG_INFO,
00064     EVENT_TERMINAL_CMD,
00065     EVENT_COUNT
00066 } SomEvent;

```

2.7.3 Function Documentation

2.7.3.1 handleSomEvent()

```

void handleSomEvent (
    SomEvent event,
    void * p_data,
    int i_data)

```

Centralized event handler for the library. This is a weak function that can be overridden by the user application.

Parameters

<i>event</i>	The event type.
<i>p_data</i>	Optional data pointer associated with the event (can be NULL).
<i>i_data</i>	Optional integer data associated with the event if specified in the event description (e.g., length of the data).

2.8 Imt_storage_manager.h File Reference

Functions

- int logError (char *text, int code)

- Writes error to app.log file.*

 - `int logWarning (char *text)`

Writes warning to app.log file.
 - `void logStringHex (uint8_t *payload, uint8_t message_length)`

Logs the given buffer as hex string.
 - `int logInfoFormatted (char *text,...)`

Variadic function for writing formatted info to app.log file.
 - `int logInfo (char *text)`

Function for writing informative string to app.log file. Creating two separate functions because most of the time we don't need to format the string.
 - `int saveSettings (void)`

Writes current device settings in JSON format to settings.txt file.
 - `void settingsFileRead (void)`

Schedules settings.txt read.
 - `int checkFwUpgradeStatus (void)`

Checks if firmware upgrade was successful or failed. Detects successful upgrades by checking if running unconfirmed image. Detects failed upgrades by checking for rejected images in secondary slot.
 - `int eraseFlash (void)`

Wrapper function for filesystem flashErase()

2.8.1 Function Documentation

2.8.1.1 checkFwUpgradeStatus()

```
int checkFwUpgradeStatus (
    void )
```

Checks if firmware upgrade was successful or failed. Detects successful upgrades by checking if running unconfirmed image. Detects failed upgrades by checking for rejected images in secondary slot.

Returns

1 if firmware upgrade was successful, 0 if no upgrade occurred, -1 if upgrade failed

2.8.1.2 eraseFlash()

```
int eraseFlash (
    void )
```

Wrapper function for filesystem flashErase()

Returns

0 on success, negative error code on fail

2.8.1.3 logError()

```
int logError (
    char * text,
    int code)
```

Writes error to app.log file.

Parameters

<i>text</i>	Error string.
<i>code</i>	Error code.

Returns

0 on success, negative value on fail

2.8.1.4 logInfo()

```
int logInfo (  
    char * text)
```

Function for writing informative string to app.log file. Creating two separate functions because most of the time we don't need to format the string.

Parameters

<i>text</i>	info message string.
-------------	----------------------

Returns

0 on success, negative value on fail

2.8.1.5 logInfoFormatted()

```
int logInfoFormatted (  
    char * text,  
    ...)
```

Variadic function for writing formatted info to app.log file.

Parameters

<i>text</i>	info message string.
-------------	----------------------

Returns

0 on success, negative value on fail

2.8.1.6 logStringHex()

```
void logStringHex (  
    uint8_t * payload,  
    uint8_t message_length)
```

Logs the given buffer as hex string.

Parameters

<i>payload</i>	pointer to the buffer
<i>message_length</i>	buffer size

2.8.1.7 logWarning()

```
int logWarning (  
    char * text)
```

Writes warning to app.log file.

Parameters

<i>text</i>	Warning string.
-------------	-----------------

Returns

0 on success, negative value on fail

2.8.1.8 saveSettings()

```
int saveSettings (  
    void )
```

Writes current device settings in JSON format to settings.txt file.

Returns

0 on success, negative value on fail

2.8.1.9 settingsFileRead()

```
void settingsFileRead (  
    void )
```

Schedules settings.txt read.

Index

- ACTIVATE_ESIM
 - lmt_settings.h, 18
- ACTIVATE_SIM
 - lmt_settings.h, 18
- ActiveSim
 - lmt_settings.h, 18
- addColumnnToTape
 - lmt_proto_handler.h, 11
- APP_COAP_MAX_MSG_LEN
 - lmt_coap_manager.h, 3
- checkBootOkMask
 - lmt_common.h, 7
- checkFwUpgradeStatus
 - lmt_storage_manager.h, 35
- criticalError
 - lmt_common.h, 8
- decodeMessage
 - lmt_proto_handler.h, 11
- disableSerialLog
 - lmt_settings.h, 18
- dumpMemory
 - lmt_proto_handler.h, 11
- enableSerialLog
 - lmt_settings.h, 18
- encodeMessage
 - lmt_proto_handler.h, 12
- eraseFlash
 - lmt_storage_manager.h, 35
- EVENT_COAP_FAIL
 - lmt_som_event_emitter.h, 33
- EVENT_COAP_NOACK
 - lmt_som_event_emitter.h, 33
- EVENT_COAP_OK
 - lmt_som_event_emitter.h, 33
- EVENT_COAP_START
 - lmt_som_event_emitter.h, 33
- EVENT_COUNT
 - lmt_som_event_emitter.h, 33
- EVENT_DEVICE_INIT_OK
 - lmt_som_event_emitter.h, 33
- EVENT_DROPPING_OLDEST
 - lmt_som_event_emitter.h, 33
- EVENT_ENQUEUE_FAILED
 - lmt_som_event_emitter.h, 33
- EVENT_LOG_ERROR
 - lmt_som_event_emitter.h, 33
- EVENT_LOG_INFO
 - lmt_som_event_emitter.h, 33
- EVENT_LOG_WARNING
 - lmt_som_event_emitter.h, 33
- EVENT_LOGGER_INIT_OK
 - lmt_som_event_emitter.h, 33
- EVENT_MAILER_INIT_OK
 - lmt_som_event_emitter.h, 33
- EVENT_MODEM_OFF
 - lmt_som_event_emitter.h, 33
- EVENT_MODEM_ON
 - lmt_som_event_emitter.h, 33
- EVENT_NETWORK_DOWN
 - lmt_som_event_emitter.h, 33
- EVENT_NETWORK_UP
 - lmt_som_event_emitter.h, 33
- EVENT_PACKER_DONE_OK
 - lmt_som_event_emitter.h, 33
- EVENT_PACKER_INIT_OK
 - lmt_som_event_emitter.h, 33
- EVENT_PACKER_STARTED
 - lmt_som_event_emitter.h, 33
- EVENT_PACKING_FAILED
 - lmt_som_event_emitter.h, 33
- EVENT_RRC_CONNECTED
 - lmt_som_event_emitter.h, 33
- EVENT_RRC_IDLE
 - lmt_som_event_emitter.h, 33
- EVENT_TERMINAL_CMD
 - lmt_som_event_emitter.h, 33
- EVENT_UL_DONE
 - lmt_som_event_emitter.h, 33
- EVENT_UL_MAX_RETRY
 - lmt_som_event_emitter.h, 33
- EVENT_UL_RETRY
 - lmt_som_event_emitter.h, 33
- EVENT_UL_START
 - lmt_som_event_emitter.h, 33
- EventHandler
 - lmt_som_event_emitter.h, 33
- FIRST_USER_STATUS_BIT
 - lmt_common.h, 7
- getActiveSim
 - lmt_settings.h, 19
- getCoapDeviceName
 - lmt_settings.h, 19
- getCoapServerHostname
 - lmt_settings.h, 19
- getCoapServerPort

- lmt_settings.h, 19
- getCoapTxFileResource
 - lmt_settings.h, 20
- getCoapTxFwResource
 - lmt_settings.h, 20
- getCoapTxResource
 - lmt_settings.h, 20
- getDeviceSN
 - lmt_coap_manager.h, 3
- getEncodedMsgBuffer
 - lmt_proto_handler.h, 12
- getEncodedMsgLen
 - lmt_proto_handler.h, 12
- getFileUIRetries
 - lmt_settings.h, 20
- getLastPeriod
 - lmt_proto_handler.h, 12
- getLogFileMaxSize
 - lmt_settings.h, 21
- getLogLevel
 - lmt_settings.h, 21
- getLogRotationFrequency
 - lmt_settings.h, 21
- getLTEConnectionTimeout
 - lmt_settings.h, 21
- getMailerWaitMode
 - lmt_coap_manager.h, 3
- getMaxResendAttempts
 - lmt_settings.h, 22
- getMaxResendTimeout
 - lmt_settings.h, 22
- getModemMode
 - lmt_settings.h, 22
- getModemModePreference
 - lmt_settings.h, 22
- getNetworkQuality
 - lmt_coap_manager.h, 4
- getNoPsmUplinkTimeout
 - lmt_settings.h, 23
- getNumOfLogFiles
 - lmt_settings.h, 23
- getPacketCounter
 - lmt_coap_manager.h, 4
- getPacketCounterLimit
 - lmt_coap_manager.h, 4
- getPsmRatTimeout
 - lmt_settings.h, 23
- getResendPacketInitialTimeout
 - lmt_settings.h, 23
- getResponseWaitTimeout
 - lmt_settings.h, 24
- getTapeRecordsCount
 - lmt_proto_handler.h, 13
- getUIDataMode
 - lmt_settings.h, 24
- getUplinkTimeout
 - lmt_settings.h, 24
- handleSomEvent

- lmt_som_event_emitter.h, 34

I_TAPE

- lmt_proto_handler.h, 10
- isCompressionCheckRequired
 - lmt_proto_handler.h, 13
- isDataChanged
 - lmt_proto_handler.h, 13
- isDeviceBatteryPowered
 - lmt_settings.h, 24
- isModemInitialized
 - lmt_coap_manager.h, 4
- isSocketConnected
 - lmt_coap_manager.h, 5
- isUdpPacketFull
 - lmt_proto_handler.h, 13
- LAST_USER_STATUS_BIT
 - lmt_common.h, 7
- lmt_coap_manager.h, 2
 - APP_COAP_MAX_MSG_LEN, 3
 - getDeviceSN, 3
 - getMailerWaitMode, 3
 - getNetworkQuality, 4
 - getPacketCounter, 4
 - getPacketCounterLimit, 4
 - isModemInitialized, 4
 - isSocketConnected, 5
 - MailerWaitModes, 3
 - modemShutdown, 5
 - resetPacketCounter, 5
 - sendEventCmdRes, 5
 - setMailerWaitMode, 5
 - setPacketCounter, 6
 - setPacketCounterLimit, 6
 - setRawData, 6
 - triggerDataPacking, 6
 - triggerMailer, 7
 - WAIT_FOREVER, 3
 - WAIT_ON_TIMEOUT, 3
- lmt_common.h, 7
 - checkBootOkMask, 7
 - criticalError, 8
 - FIRST_USER_STATUS_BIT, 7
 - LAST_USER_STATUS_BIT, 7
 - resetStatusBit, 8
 - setBootOkBit, 8
 - setUserBootOkMask, 8
- lmt_monitor.h, 9
 - logResetReason, 9
 - saveResetRegister, 9
- lmt_proto_handler.h, 9
 - addColumnToTape, 11
 - decodeMessage, 11
 - dumpMemory, 11
 - encodeMessage, 12
 - getEncodedMsgBuffer, 12
 - getEncodedMsgLen, 12
 - getLastPeriod, 12

- getTapeRecordsCount, 13
- I_TAPE, 10
- isCompressionCheckRequired, 13
- isDataChanged, 13
- isUdpPacketFull, 13
- MAX_ACTION_PARAMETERS_SIZE, 10
- MAX_COLUMNS_COUNT, 10
- MAX_PERIODS_COUNT, 10
- MAX_TAPE_COUNT, 11
- MAX_TRACKS_COUNT, 11
- restartMeasurements, 14
- rewindTape, 14
- updatePeriod, 14
- lmt_sdk_api.h, 15
 - lmtInit, 15
 - loop, 15
 - setup, 15
- lmt_settings.h, 15
 - ACTIVATE_ESIM, 18
 - ACTIVATE_SIM, 18
 - ActiveSim, 18
 - disableSerialLog, 18
 - enableSerialLog, 18
 - getActiveSim, 19
 - getCoapDeviceName, 19
 - getCoapServerHostname, 19
 - getCoapServerPort, 19
 - getCoapTxFileResource, 20
 - getCoapTxFwResource, 20
 - getCoapTxResource, 20
 - getFileUIRetries, 20
 - getLogFileMaxSize, 21
 - getLogLevel, 21
 - getLogRotationFrequency, 21
 - getLTEConnectionTimeout, 21
 - getMaxResendAttempts, 22
 - getMaxResendTimeout, 22
 - getModemMode, 22
 - getModemModePreference, 22
 - getNoPsmUplinkTimeout, 23
 - getNumOfLogFiles, 23
 - getPsmRatTimeout, 23
 - getResendPacketInitialTimeout, 23
 - getResponseWaitTimeout, 24
 - getUIDataMode, 24
 - getUplinkTimeout, 24
 - isDeviceBatteryPowered, 24
 - LOG_ERRORS, 18
 - LOG_INFORMATIVE, 18
 - LOG_WARNINGS, 18
 - LogLevel, 18
 - printCoap, 25
 - scanForCoapKeys, 25
 - setActiveSim, 25
 - setCoapServerHostname, 25
 - setCoapServerPort, 26
 - setCoapTxFileResource, 26
 - setCoapTxFwResource, 26
 - setCoapTxResource, 26
 - setFileUIRetries, 27
 - setLogFileMaxSize, 27
 - setLogLevel, 27
 - setLogRotationFrequency, 27
 - setLTEConnectionTimeout, 28
 - setMaxResendAttempts, 28
 - setMaxResendTimeout, 28
 - setModemMode, 29
 - setModemModePreference, 29
 - setNoPsmUplinkTimeout, 29
 - setNumOfLogFiles, 30
 - setPowerOption, 30
 - setPsmRatTimeout, 30
 - setResendPacketInitialTimeout, 31
 - setResponseWaitTimeout, 31
 - setUIDataMode, 31
 - setUplinkTimeout, 32
- lmt_som_event_emitter.h, 32
 - EVENT_COAP_FAIL, 33
 - EVENT_COAP_NOACK, 33
 - EVENT_COAP_OK, 33
 - EVENT_COAP_START, 33
 - EVENT_COUNT, 33
 - EVENT_DEVICE_INIT_OK, 33
 - EVENT_DROPPING_OLDEST, 33
 - EVENT_ENQUEUE_FAILED, 33
 - EVENT_LOG_ERROR, 33
 - EVENT_LOG_INFO, 33
 - EVENT_LOG_WARNING, 33
 - EVENT_LOGGER_INIT_OK, 33
 - EVENT_MAILER_INIT_OK, 33
 - EVENT_MODEM_OFF, 33
 - EVENT_MODEM_ON, 33
 - EVENT_NETWORK_DOWN, 33
 - EVENT_NETWORK_UP, 33
 - EVENT_PACKER_DONE_OK, 33
 - EVENT_PACKER_INIT_OK, 33
 - EVENT_PACKER_STARTED, 33
 - EVENT_PACKING_FAILED, 33
 - EVENT_RRC_CONNECTED, 33
 - EVENT_RRC_IDLE, 33
 - EVENT_TERMINAL_CMD, 33
 - EVENT_UL_DONE, 33
 - EVENT_UL_MAX_RETRY, 33
 - EVENT_UL_RETRY, 33
 - EVENT_UL_START, 33
 - EventHandler, 33
 - handleSomEvent, 34
 - SomEvent, 33
- lmt_storage_manager.h, 34
 - checkFwUpgradeStatus, 35
 - eraseFlash, 35
 - logError, 35
 - logInfo, 36
 - logInfoFormatted, 36
 - logStringHex, 36
 - logWarning, 37

- saveSettings, 37
- settingsFileRead, 37
- lmtInit
 - lmt_sdk_api.h, 15
- LOG_ERRORS
 - lmt_settings.h, 18
- LOG_INFORMATIVE
 - lmt_settings.h, 18
- LOG_WARNINGS
 - lmt_settings.h, 18
- logError
 - lmt_storage_manager.h, 35
- logInfo
 - lmt_storage_manager.h, 36
- logInfoFormatted
 - lmt_storage_manager.h, 36
- LogLevel
 - lmt_settings.h, 18
- logResetReason
 - lmt_monitor.h, 9
- logStringHex
 - lmt_storage_manager.h, 36
- logWarning
 - lmt_storage_manager.h, 37
- loop
 - lmt_sdk_api.h, 15
- MailerWaitModes
 - lmt_coap_manager.h, 3
- MAX_ACTION_PARAMETERS_SIZE
 - lmt_proto_handler.h, 10
- MAX_COLUMNS_COUNT
 - lmt_proto_handler.h, 10
- MAX_PERIODS_COUNT
 - lmt_proto_handler.h, 10
- MAX_TAPE_COUNT
 - lmt_proto_handler.h, 11
- MAX_TRACKS_COUNT
 - lmt_proto_handler.h, 11
- modemShutdown
 - lmt_coap_manager.h, 5
- printCoap
 - lmt_settings.h, 25
- resetPacketCounter
 - lmt_coap_manager.h, 5
- resetStatusBit
 - lmt_common.h, 8
- restartMeasurements
 - lmt_proto_handler.h, 14
- rewindTape
 - lmt_proto_handler.h, 14
- saveResetRegister
 - lmt_monitor.h, 9
- saveSettings
 - lmt_storage_manager.h, 37
- scanForCoapKeys
 - lmt_settings.h, 25
- sendEventCmdRes
 - lmt_coap_manager.h, 5
- setActiveSim
 - lmt_settings.h, 25
- setBootOkBit
 - lmt_common.h, 8
- setCoapServerHostname
 - lmt_settings.h, 25
- setCoapServerPort
 - lmt_settings.h, 26
- setCoapTxFileResource
 - lmt_settings.h, 26
- setCoapTxFwResource
 - lmt_settings.h, 26
- setCoapTxResource
 - lmt_settings.h, 26
- setFileUIRetries
 - lmt_settings.h, 27
- setLogFileMaxSize
 - lmt_settings.h, 27
- setLogLevel
 - lmt_settings.h, 27
- setLogRotationFrequency
 - lmt_settings.h, 27
- setLTEConnectionTimeout
 - lmt_settings.h, 28
- setMailerWaitMode
 - lmt_coap_manager.h, 5
- setMaxResendAttempts
 - lmt_settings.h, 28
- setMaxResendTimeout
 - lmt_settings.h, 28
- setModemMode
 - lmt_settings.h, 29
- setModemModePreference
 - lmt_settings.h, 29
- setNoPsmUplinkTimeout
 - lmt_settings.h, 29
- setNumOfLogFiles
 - lmt_settings.h, 30
- setPacketCounter
 - lmt_coap_manager.h, 6
- setPacketCounterLimit
 - lmt_coap_manager.h, 6
- setPowerOption
 - lmt_settings.h, 30
- setPsmRatTimeout
 - lmt_settings.h, 30
- setRawData
 - lmt_coap_manager.h, 6
- setResendPacketInitialTimeout
 - lmt_settings.h, 31
- setResponseWaitTimeout
 - lmt_settings.h, 31
- settingsFileRead
 - lmt_storage_manager.h, 37
- setUIDataMode

- lmt_settings.h, 31
- setup
 - lmt_sdk_api.h, 15
- setUplinkTimeout
 - lmt_settings.h, 32
- setUserBootOkMask
 - lmt_common.h, 8
- SomEvent
 - lmt_som_event_emitter.h, 33
- triggerDataPacking
 - lmt_coap_manager.h, 6
- triggerMailer
 - lmt_coap_manager.h, 7
- updatePeriod
 - lmt_proto_handler.h, 14
- WAIT_FOREVER
 - lmt_coap_manager.h, 3
- WAIT_ON_TIMEOUT
 - lmt_coap_manager.h, 3